

ThreatQuotient



Intelligence Mailbox Reports Connector Guide

Version 1.0.0

September 06, 2022

ThreatQuotient

20130 Lakeview Center Plaza Suite 400
Ashburn, VA 20147



ThreatQ Supported

Support

Email: support@threatq.com

Web: support.threatq.com

Phone: 703.574.9893

Contents

Integration Details	5
Introduction	6
Prerequisites	7
Time Zone	7
Integration Dependencies	8
Installation	9
Creating a Python 3.6 Virtual Environment	9
Installing the Connector	10
Configuration	12
Usage	14
Command Line Arguments.....	14
CRON.....	16
Change Log	17

Warning and Disclaimer

ThreatQuotient, Inc. provides this document “as is”, without representation or warranty of any kind, express or implied, including without limitation any warranty concerning the accuracy, adequacy, or completeness of such information contained herein. ThreatQuotient, Inc. does not assume responsibility for the use or inability to use the software product as a result of providing this information.

Copyright © 2022 ThreatQuotient, Inc.

All rights reserved. This document and the software product it describes are licensed for use under a software license agreement. Reproduction or printing of this document is permitted in accordance with the license agreement.

Support

This integration is designated as **ThreatQ Supported**.

Support Email: support@threatq.com

Support Web: <https://support.threatq.com>

Support Phone: 703.574.9893

Integrations/apps/add-ons designated as **ThreatQ Supported** are fully supported by ThreatQuotient's Customer Support team.

ThreatQuotient strives to ensure all ThreatQ Supported integrations will work with the current version of ThreatQuotient software at the time of initial publishing. This applies for both Hosted instance and Non-Hosted instance customers.



ThreatQuotient does not provide support or maintenance for integrations, apps, or add-ons published by any party other than ThreatQuotient, including third-party developers.

Integration Details

ThreatQuotient provides the following details for this integration:

Current Integration Version	1.0.0
Compatible with ThreatQ Versions	>= 4.34.0
Python Version	3.6
Support Tier	ThreatQ Supported
ThreatQ Marketplace	https://marketplace.threatq.com/details/intelligence-mailbox-reports-connector

Introduction

The Intelligence Mailbox Reports Connector for ThreatQ enables analysts to use an email inbox for spearphish submissions as well as intelligence sharing. The email itself will be added as a File in ThreatQ, with its articles added as related Reports and all IoCs or other attachments found in the email related correspondingly.

This integration is based on the IMAP Connector for ThreatQ integration with the following updated processes:

- Modifies to upload a report (with corresponding attributes) to TQ for each article in the email instead of one event for the whole email.
- Adds TLP as attributes.
- Adds the entire email as a related Attachment.
- Relates IoCs in articles to article Reports.
- Removes forwarded email spearphish functionality.

Prerequisites

Review the following requirements before attempting to install the connector.

Time Zone

You should ensure all ThreatQ devices are set to the correct time, time zone, and date (UTC is recommended), and using a clock source available to all.

To identify which time zone is closest to your present location, use the `timedatectl` command with the `list-timezones` command line option.


For example, enter the following command to list all available time zones in Europe:

```
timedatectl list-timezones | grep Europe
Europe/Amsterdam
Europe/Athens
Europe/Belgrade
Europe/Berlin
```

Enter the following command, as root, to change the time zone to UTC:

```
timedatectl set-timezone UTC
```

Integration Dependencies

 The integration must be installed in a python 3.6 environment.

The following is a list of required dependencies for the integration. These dependencies are downloaded and installed during the installation process. If you are an Air Gapped Data Sync (AGDS) user, or run an instance that cannot connect to network services outside of your infrastructure, you will need to download and install these dependencies separately as the integration will not be able to download them during the install process.



Items listed in bold are pinned to a specific version. In these cases, you should download the version specified to ensure proper function of the integration.

DEPENDENCY	VERSION	NOTES
threatqsdk	>=1.8.2	N/A
threatqcc	>=1.4.1	N/A
PySocks	>=1.6.7	N/A
beautifulsoup4	4.9.3	Pinned

Installation

The following provides you with steps on installing a Python 3 Virtual Environment and installing the connector.


Creating a Python 3.6 Virtual Environment

Run the following commands to create the virtual environment:

```
mkdir /opt/tqvenv/  
sudo yum install -y python36 python36-libs python36-devel python36-pip  
python3.6 -m venv /opt/tqvenv/<environment_name>  
source /opt/tqvenv/<environment_name>/bin/activate  
pip install --upgrade pip  
pip install threatqsdk threatqcc  
pip install setuptools==59.6.0
```

Proceed to [Installing the Connector](#).

Installing the Connector

 **Upgrading Users** - Review the [Change Log](#) for updates to configuration parameters before updating. If there are changes to the configuration file (new/removed parameters), you must first delete the previous version's configuration file before proceeding with the install steps listed below. Failure to delete the previous configuration file will result in the connector failing.

1. Navigate to the ThreatQ Marketplace and download the .whl file for the integration.
2. Activate the virtual environment if you haven't already:

```
<> source /opt/tqvenv/<environment_name>/bin/activate
```

3. Transfer the whl file to the /tmp directory on your ThreatQ instance.
4. Install the connector on your ThreatQ instance:

```
<> pip install /tmp/tq_conn_intel_mailbox_reports-<version>-py3-none-any.whl
```



A driver called tq-conn-intel-mailbox-reports will be installed. After installing, a script stub will appear in /opt/tqvenv/<environment_name>/bin/tq-conn-intel-mailbox-reports.

5. Once the application has been installed, a directory structure must be created for all configuration, logs and files, using the `mkdir -p` command. Use the commands below to create the required directories:

```
<> mkdir -p /etc/tq_labs/  
mkdir -p /var/log/tq_labs/
```

6. Perform an initial run using the following command:

```
<> /opt/tqvenv/<environment_name>/bin/tq-conn-intel-mailbox-reports -ll /var/log/tq_labs/ -c /etc/tq_labs/ -v3
```

7. Enter the following parameters when prompted:

PARAMETER	DESCRIPTION
ThreatQ Host	This is the host of the ThreatQ instance, either the IP Address or Hostname as resolvable by ThreatQ.
ThreatQ Client ID	This is the OAuth id that can be found at Settings Gear → User Management → API details within the user's details.
ThreatQ Username	This is the Email Address of the user in the ThreatQ System for integrations.
ThreatQ Password	The password for the above ThreatQ account.
Status	This is the default status for objects that are created by this Integration.

Example Output

```
/opt/tqvenv/<environment_name>/bin/tq-conn-intel-mailbox-reports -ll /var/log/tq_labs/ -c /etc/tq_labs/ -v3
ThreatQ Host: <ThreatQ Host IP or Hostname>
ThreatQ Client ID: <ClientID>
ThreatQ Username: <EMAIL ADDRESS>
ThreatQ Password: <PASSWORD>
Status: Review
Connector configured. Set information in UI
```

You will still need to [configure and then enable the connector](#).

Configuration




ThreatQuotient does not issue API keys for third-party vendors. Contact the specific vendor to obtain API keys and other integration-related credentials.

To configure the integration:

1. Navigate to your integrations management page in ThreatQ.
2. Select the **Labs** option from the *Category* dropdown (optional).
3. Click on the integration entry to open its details page.
4. Enter the following parameters under the **Configuration** tab:

PARAMETER	DESCRIPTION
Intelligence Mailbox Server	The Intelligence Mailbox server associated with the email provider you want to connect.
Intelligence Mailbox Username	The username/email to log into.
Intelligence Mailbox Password	The password associated with the account above.
Proxy Address	Optional - Socks proxy address used to connect to the Intelligence Mailbox server. This cannot be a HTTP/HTTPS proxy, that is why the proxy settings within ThreatQ will not be used.
Proxy Port	Optional - The port associated with the proxy address field.
Proxy Port	Optional - The type of proxy that will be used. The options are <i>socks4</i> and <i>socks5</i> .



Disabled

☒

Enabled

Additional Information

Integration Type: Connector

Configuration

Intelligence Mailbox Server

x.x.x.x

Intelligence Mailbox Server

Intelligence Mailbox Username

username

Intelligence Mailbox Username

Intelligence Mailbox Password

Intelligence Mailbox Password

Proxy Address

Proxy Address

Proxy Port

Proxy Port

Proxy Type

Socks4

Proxy Type

Save

- Review any additional settings, make any changes if needed, and click on **Save**.
- Click on the toggle switch, located above the *Additional Information* section, to enable it.

Usage

Use the following command to execute the driver:

```
<> /opt/tqvenv/<environment_name>/bin/tq-conn-intel-mailbox-reports -  
v3 -ll /var/log/tq_labs/ -c /etc/tq_labs/
```

Command Line Arguments

This connector supports the following custom command line arguments:

ARGUMENT	DESCRIPTION
<code>-h, --help</code>	Review all additional options and their descriptions.
<code>-ll LOGLOCATION, --loglocation LOGLOCATION</code>	Sets the logging location for the connector. The location should exist and be writable by the current. A special value of 'stdout' means to log to the console (this happens by default).
<code>-c CONFIG, --config CONFIG</code>	This is the location of the configuration file for the connector. This location must be readable and writable by the current user. If no config file path is given, the current directory will be used. This file is also where some information from each run of the connector may be put (last run time, private oath, etc.)
<code>-v {1,2,3}, --verbosity {1,2,3}</code>	This is the logging verbosity level where 3 means everything.
<code>-n, --name</code>	Optional - Name of the connector (Option used in order to allow users to configure multiple Intelligence Mailbox connector instances on the same TQ box).

ARGUMENT	DESCRIPTION
<code>--external-proxy, -ep</code>	This enables a proxy to be used to contact the internet for the data required by this connector. This specifies an internet facing proxy, NOT a proxy to the TQ instance.
<code>-d, --no-differential</code>	If exports are used in this connector, this will turn 'off' the differential flag for the execution. This allows debugging and testing to be done on export endpoints without having to rebuild the exports after the test. THIS SHOULD NEVER BE USED IN PRODUCTION.
<code>-f FILES, --files FILES</code>	Directory where downloaded files are kept.
<code>-ds, --disable_ssl</code>	Enables the ability to specify port 143 instead of 993.

CRON

Automatic CRON configuration has been removed from this script. To run this script on a recurring basis, use CRON or some other jobs scheduler. The argument in the CRON script must specify the config and log locations.

Add an entry to your Linux crontab to execute the connector at a recurring interval. Depending on how quickly you need updates, this can be run multiple times a day (no more than once an hour) or a few times a week.

In the example below, the command will execute the connector every two hours.

1. Log into your ThreatQ host via a CLI terminal session.
2. Enter the following command:

```
<> crontab -e
```

This will enable the editing of the crontab, using vi. Depending on how often you wish the cronjob to run, you will need to adjust the time to suit the environment.

3. Enter the commands below:

Every 2 Hours Example

```
<> 0 */2 * * * /opt/tqenv/<environment_name>/bin/tq-conn-intel-  
mailbox-reports -c /etc/tq_labs/ -ll /var/log/tq_labs/ -v3
```

4. Save and exit CRON.

Change Log

- Version 1.0.0
 - Initial release