ThreatQuotient



ThreatQ User Guide

Version 4.54.0

July 27, 2021

ThreatQuotient

11400 Commerce Park Dr., Suite 200 Reston, VA 20191

Support

Email: support@threatq.com

Web: support.threatq.com

Phone: 703.574.9893



Warning and Disclaimer

ThreatQuotient, Inc. provides this document "as is", without representation or warranty of any kind, express or implied, including without limitation any warranty concerning the accuracy, adequacy, or completeness of such information contained herein. ThreatQuotient, Inc. does not assume responsibility for the use or inability to use the software product as a result of providing this information.

Copyright © 2021 ThreatQuotient, Inc.

All rights reserved. This document and the software product it describes are licensed for use under a software license agreement. Reproduction or printing of this document is permitted in accordance with the license agreement.



Contents

About the ThreatQ Platform	
Concept	
Threat Library	
Adaptive Workbench	
Open Exchange	
Accessing the Platform	
Authentication Methods	
Transitioning Authentication Methods	
Platform Login	17
Local Log in	17
Single Sign-On (SSO)	
2-Step Verification	19
Enabling 2-Step Verification	
Air Gapped Data Sync (AGDS)	20
System Requirements	
Executing Air Gapped Data Sync	
Running the threatq:sync-export Command	
Running the threatq:sync-import Command	
threatq:sync-import	
Parameters	
Examples	
Initial Setup	
Run Scenarios	
Data Processing	
Basic Table	
Tables with Pivots	
File Output	
threatq sync-import File Output and Sync Report	
threatq:sync-import Command Line Output	
Synchronizations	
threatq:sync-export	
Parameters	
Examples	
Initial Cron for First Time Use	
Run Scenarios	
Dates	
Configuration	
Output and Sync Report	
Meta Data	
Meta Data Objects	
Objects	
Object Context	
Other Data	
File Output	
Command Line Output	
Synchronizations	
Upgrading an Air Gapped ThreatQ Instance	
Backup and Restore	
ThreatQ Backup	
ThreatQ Restore	
Command Line Interface (CLI)	49



Maintenance Mode	
Placing the ThreatQ Application into Maintenance Mode	49
Taking the ThreatQ Application out of Maintenance Mode	50
Commands	51
Auto Configuration MariaDB Command	51
System ThreatQ Purge	51
Add/Upgrade CDF	52
Source Consolidation	54
Source Merge	55
Historic Pull	57
Merge Attributes	58
iSight Historic Pull	59
Threat Intelligence Services Custom Feeds Historic Pull Commands	60
Reset User Password	60
Update TLP Designations	60
Convert TLP	62
View Feed Queues	63
Airgap Import	64
Airgap Export	64
Dashboards	65
Default Dashboard	66
Overview by Intelligence Score	66
Incoming Intelligence	67
Watchlist Activity	68
Tasks	69
Custom Dashboards	70
Analytics Dashboards	72
Adversaries Analytics Dashboard	73
Adversaries Summary Table	73
Adversaries Overlap Table	74
Indicator Distribution Pie Chart	75
Events Analytics Dashboard	77
Events History Scatter Plot	78
Monthly Heatmap	
New Events Summary	81
Files Analytics Dashboard	83
Files Pie Chart	84
Files Table	85
Indicators Analytics Dashboard	87
Recently Created Indicators Histogram	
Most Recent 100 Indicators	
Attributes Table	
Recent Sources	
Attack Phases	
Dashboard Widgets	
Bar Chart	
Description	98
Line Chart	
Count	
Pie Chart	
Table	
Dashboard Management	
Accessing a Dashboard	
Add an Existing Dashboard to Your View	
Creating a Dashboard	
Editing a Dashboard	
U	



Deleting a Dashboard	111
Reassigning a Dashboard of a Deleted User	
Dashboard Sharing	
Sharing a Dashboard	
Updating Dashboard Permissions	
Shared Dashboards of a Deleted User	
Dashboard Export	
Creating a Dashboard PDF	
User View Management	
Adding a Dashboard to Your View	
Removing a Dashboard from Your View	
Changing Dashboard Order	
Data Controls	
Indicator Expiration	
Accessing the Indicator Expiration Page	
How ThreatQ Calculates Expiration Dates	
Selecting an Expiration Policy per Feed	
Adding Exceptions	
Applying Expiration Policy Changes to Data	
Common Expiration Policy Scenarios	
Scoring Algorithms	
Accessing the Scoring Sensitivity Page	
Scoring Criteria	
Configuring Your Scoring Algorithm	
Traffic Light Protocol (TLP)	
Designations	
TLP Assignment Hierarchy	
Access TLP Settings	
Configure TLP Visibility	
Apply a TLP Designation to Source	
Whitelisted Indicators	
Accessing the Whitelisted Indicator Rules	
Creating a Whitelisted Rule	
Editing a Whitelisted Rule	
Removing a Whitelisted Rule	
Exports	
Managing Exports	
Accessing the Exports List	
Viewing an Export	
Enabling/Disabling Exports	
Adding an Export	
Duplicating an Export	
Editing an Export's Connection Settings	
Editing an Export's Output Format	
Deleting an Export	147
Output Format Options	
Customizing the Output Format Template	149
Adding Special Parameters	149
Adding Differential Flags	163
Adding Parameters to the end of the URL	164
Using Logical Operators in Export Filters	164
Output Format Templates	166
Adversaries Template	166
Events Template	166
Indicators Template	167
Signatures Template	167



Template Variables	168
Source Variable	168
Attribute Variable	168
Adversary Variable	168
Attachment Variable	169
Event Variable	169
Indicator Variable	
Investigation Variable	
Signature Variable	
Task Variable	
Specific Indicator Exports	
Cisco TID Exports	
Fidelis Exports	
Fortinet Fortigate Exports	
Lancope Exports	
Netwitness Exports	
OpenIOC Signature Exports	
Palo Alto Exports	
Palo Alto: PANOS and Panorama Exports	
Reservoir Labs Exports	
Splunk Exports	
Symantec ProxySG Exports	
Tenable Exports	
Zeek Exports	
Integrations Management	
Accessing Integrations Management	
Integration Types	
Threat Intelligence Feed Categories	
Operations	
Managing Integrations	
Adding Integrations	
Adding STIX/TAXII Integrations	
Configuring an Integration	
Feed Health Notifications	
Enabling/Disabling Integrations	
Removing an Integration	
Performing Manual Runs (feeds)	
Running an Operation Integration	
Integration-Related Commands	
Activity Log (feeds)	
Accessing an Intel Feed's Activity Log	
lob Management	
Licensing	
Managing Your ThreatQ License	
Viewing License Status	
Updating a License	
Navigation Menu	
Notifications	
Feed Health Email Notifications	
Configuring Mail Server	
Enabling Feed Health Notifications	
Notification Center	
Object Management	
Indicator Statuses Management	
Indicator Status Assignment	
Indirect Indicator Status	
	200



	Protected Indicator Statuses	. 266
	Viewing Indicator Statuses	. 266
	Suppressing Indicator Status Updates	
	Adding an Indicator Status	. 268
	Editing an Indicator Status	. 269
	Deleting an Indicator Status	. 270
	Indicator Types	. 272
	Event Types	. 274
	Viewing Event Types	. 275
	Adding an Event Type	. 276
	Editing an Event Type	. 278
	Deleting an Event Type	
Re	oorts	. 282
•	Generating Reports	. 282
	Turning Off the Pop-Up Blocker in Chrome	. 282
	Report Options	. 283
	Customizing the Report Header	. 283
	Customizing Report Text Colors	. 283
	Adding a Custom Disclaimer to a Report	. 284
	Previewing Report Customization	. 284
Sei	ver Administration	. 285
	ThreatQ Monitoring Platform	. 285
	Creating a User Account for the ThreatQ Monitoring Platform	. 285
	Accessing the ThreatQ Monitoring Platform	. 286
Sh	aring	. 289
	User Permission Levels	. 289
	User Permission Levels and User Roles	. 290
	View-Only Permissions for All Users	. 290
	Permission Conversion	. 291
	Permission Levels and Integrations	. 291
Sys	tem Configuration	. 292
	Proxy	. 293
	Accessing Proxy Configuration	. 293
	Account Security	. 295
	User Lockout Settings	. 295
	Configuring User Lockout Settings	. 295
	Custom Login Banner	. 296
	Banner Behavior	. 296
	Enabling a Custom Banner	. 297
	General Settings	. 301
	Configuring Date and Time Format	. 301
	Configuring Indicator Parsing Presets	. 302
	Opt In/ Opt Out of Product Analytics	. 304
Sys	tem Objects	. 306
	Adversaries	. 307
	Adding Adversaries	. 307
	Adding Context	. 308
	Editing Adversaries	. 308
	Deleting Adversaries	. 309
	Attack Patterns	. 311
	Adding an Attack Patterns	. 311
	Adding Context	. 312
	Editing an Attack Pattern	. 312
	Deleting an Attack Pattern	. 313
	Campaigns	. 315
	Adding a Campaign	. 315



Adding Context	317
Editing a Campaign	317
Deleting a Campaign	318
Courses of Action	320
Adding a Course of Action	320
Adding Context	321
Editing a Course of Action	
Deleting a Course of Action	
Events	
Adding Events	
Adding Context	
Editing Events	
Deleting Events	
Files	
Adding Files	
Adding Context	
Editing Files	
Deleting Files	
Identities	
Adding an Identity	
5	
Adding Context	
Deleting an Identity	
Incidents	
Adding an Incident	
Adding Context	
Deleting an Incident	
Indicators	
Adding an Indicator	
Adding Context	
Editing Indicators	
Deleting an Indicator	
Parsing for an Indicator	
Indicator Expiration	
Ways an Indicator can Expire	
Changing the Expiration Date for an Individual Indicator	
Changing the Expiration Date for Multiple Indicators	
Indicator Scoring	360
Building a Scoring Algorithm	360
Setting a Manual Indicator Score	360
Indicator Status	362
Default Statuses	362
Custom Statuses	363
Changing the Status of an Individual Indicator	363
Changing the Status for Multiple Indicators	364
Indicator URL Normalization	365
Importing Indicators via CSV	368
CSV Columns	368
Parsing a Threatq CSV File and Adding Context	371
Troubleshooting	376
Supported Defanging Techniques	
Intrusion Sets	
Adding an Intrusion Set	
Adding Context	
Deleting an Intrusion Set	
Malware	
Adding a Malware Object	
0	



Adding Context	3	385
Editing a Malware Object	3	385
Deleting a Malware Object	3	386
Reports	3	388
Adding an Reports	3	388
Adding Context		
Editing an Report		
Deleting an Report		
Signatures		
Adding a Signature		
STIX		
ThreatQ STIX Object Types		
Parsing a STIX File for Indicators		
STIX 1.1.1, 1.2 Data Mapping		
STIX 1111, 112 Butta Mapping		
Tasks		
Assigning a Task		
Managing Tasks		
Threat Library Managing Your Library View		
Selecting Object Type View		
Basic Search		
Performing a Basic Search		
Wildcards and Symbols in Searches		
Creating an Object During a Basic Search		
Building Searches with Filter Sets		
Adding Filter Sets		
Deleting Filter Sets		
And/Or Order of Operations		
Context Filters		
Filtering by Attribute		
Using Multiple Attribute Filters		
Filtering by CIDR Block Range		
Filtering by Value Contains		
Filtering by List of Indicators		
Filtering by Keyword		160
Filtering by Relationship		
Filtering by Related Object Type		
Filtering by Score	4	166
Filtering by Tags	4	168
Filtering by Source	4	169
Filtering by TLP	4	171
Date Filters	4	173
Filtering by Date Created	4	173
Filtering by Last Modified	4	174
Filtering by Published Date	4	175
Filtering by Source Ingest Time	4	1 77
Filtering by Expiration Date		
Status Filters		
Filtering by Status		
Tasks Filters		
Filtering Tasks by Assignment		
Filtering Tasks by Due Date		
Filtering Tasks by Priority		
Filtering Tasks by Reported By		
········ 0 · ···	т	



Type Filters	40-
Filtering by Object Type	
Managing Search Results	
Saving Searches as Data Collections	
Loading Data Collections	
Modifying a Data Collection	
Copying a Data Collection	
Renaming a Data Collection	
Sharing Data Collections	
Removing a User's Access to a Data Collection	
Deleting a Data Collection	
Exporting Search Results to CSV	
Bulk Actions	
Bulk Add Source	500
Bulk Add/Remove Attributes	
Bulk Add/Remove Attribute Scenarios	504
Bulk Add/Remove Tags	500
Bulk Change Expiration Date	508
Bulk Expiration Change Scenarios	510
Bulk Delete	51 <i>°</i>
Bulk Add/Remove Relationships	514
Bulk Status Change	517
Object Details	520
Adding/Removing an Object to the Watchlist	
Actions Menu	
Context Panes	
Attributes Pane	
Adding an Attribute to an Object	
Deleting an Attribute from an Object	
Deleting an Attribute Source from an Object	
Sources Pane	
Adding a Source to an Object	
Tags Pane	
Adding a Tag to an Object	
Deleting a Tag from an Object	
Description Pane	
Updating the Description of an Object	
Relationships Panes	
Linking a System Object	
Unlinking a System Object	
Additional Related Object Actions	
Adding a comment to a related adversary	
·	
Editing a related adversary comment	
Deleting a related adversary comment	
Related Adversaries - Confidence Level	
Related Indicators - Bulk Actions	
Comments Pane	
Adding Comments to an Object	
Editing Comments for an Object	
Deleting Comments from an Objects	
Audit Log	
Froubleshooting	
Generating a Troubleshooting Package	
SSL Certificates	
Unable to Verify SSL Certificate	
Configuring Custom SSL Certificates (not self-signed)	546



ThreatQ Critical System Processes	548
Date and Time Stamps in ThreatQ	550
User Management	552
Managing User Accounts	553
Accessing Your User Account	553
Accessing Other User Accounts	553
User Account Properties	554
Adding a User	555
Editing a User	
Resetting User Password from the Command Line	557
Deleting a User	
Updating User Avatar	
User Roles	
LDAP Authentication	561
Required Information for Creating LDAP Authentication	562
Switching LDAP Connections	
Anonymous Bind	564
Configuring Secure LDAP	567
Authenticated Bind	
SAML Authentication	575
Configuring SAML	575
Setting Up LDAP Users/Groups for SAML	581
Adding ThreatQ as a Service Provider	587
ADFS 2016	587
Azure AD	591
Google G Suite	593
Okta	597
Index	CO1



About the ThreatQ Platform

ThreatQ is a cyber threat intelligence platform that focuses on centralizing, structuring, and strengthening a security organization's intelligence-driven defensive posture against attacks.

Concept

The following describes how ThreatQ helps organizations manage threat intelligence, allowing them to defend against sophisticated cyber-attacks.

Threat Library

A central repository combining global and local threat data to provide relevant and contextual intelligence that is customized for your unique environment. Over time, the library becomes more and more tuned to your environment and fills in the intelligence gaps created by different sources, all providing only some pieces of the puzzle.

Adaptive Workbench

An open and extensible work area for security experts across the organization to work within your processes and tools. A customizable workflow and customer-specific enrichment streamlines investigations and analysis, and automates the intelligence life cycle.

Open Exchange

ThreatQ is the only threat intelligence platform specifically designed for customization to meet the requirements of your unique environment. Get more from your existing security investments by integrating your tools, teams and workflows through standard interfaces and an SDK/API for customization.



Accessing the Platform

To access the ThreatQ web UI, you must authenticate yourself with a username and password. You can use the main menu to access ThreatQ functionality.

User sessions time out after 60 minutes of inactivity. Users with administrator and maintenance roles can update this setting or, disable session timeouts for that specific user, by viewing the user's account profile. See the *Editing a User* section of the Managing User Accounts topic for more details.



The initial account created when installing ThreatQ does not have a set session time by default. This setting can be updated as well from the user profile account.



Authentication Methods

There are three authentication methods that can used to access your ThreatQ platform:

METHOD	DESCRIPTION	REFERENCE
Local Authentication	User accounts are created and maintained manually within in the platform. Username, passwords, and permission roles are configured within ThreatQ. Administrators can edit a user's profile including email, password, and permission role in ThreatQ. Local users will log in using the local user login method for the ThreatQ platform.	 User Management Accessing the Platform
LDAP Authentication	User accounts are created and authenticated outside of the ThreatQ platform and user roles are mapped from the user's Active Directory. Due to this nature, user accounts cannot be modified within the ThreatQ platform (User Management page). LDAP users will log in using the local user login option for the ThreatQ platform - see Local Login.	• LDAP Authentication
SAML Authentication	User accounts are created and authenticated outside of the ThreatQ platform and user roles are mapped from the user's Active Directory. Due to this nature, user accounts cannot be modified within the ThreatQ platform (User Management page). SAML does not allow user role mapping for maintenance accounts. SAML users will log in using the single sign-on	• SAML Authentication



METHOD	DESCRIPTION	REFERENCE

(SSO) login option for the ThreatQ platform see SSO Login.

Transitioning Authentication Methods

The following scenarios will detail how authentication methods can be transitioned in the ThreatQ platform.

CURRENT METHOD	NEW METHOD	DETAILS
Local SAML		Current ThreatQ accounts will be mapped using the user's email address and users will use SSO to log into the platform - see SSO Login. Local Maintenance Accounts will not be mapped in SAML and will continue to use the local login method. See the Configuring SAML topic for details on this setup process.
		⚠ ThreatQuotient strongly recommends that you perform a full backup before changing your authentication method.

SAML	Local	Contact ThreatQ Support.
Local	LDAP	Current ThreatQ accounts will be mapped using the user's email address and users will continue to use the local login method - see Local Login. See the LDAP Authentication topic for details on this setup process.



ThreatQuotient strongly recommends that you perform a full backup before changing your authentication method.



CURRENT METHOD	NEW METHOD	DETAILS
LDAP	Local	Contact ThreatQ Support.
LDAP	SAML	LDAP must be disabled before enabling SAML. No account updates are required if the unique account identifier for LDAP was the user's email address. The LDAP group that is mapped to the ThreatQ Maintenance role will have to be mapped to different user role as SAML does not allow maintenance account mapping.
SAML	LDAP	SAML must be disabled before enabling LDAP. No account updates are required if the unique account identifier for SAML was the user's email address.



Platform Login

When you installed ThreatQ, you defined an IP address for the web UI, and set up the *Maintenance Account* and password.

There are two methods that can be used to log into your ThreatQ instance:

- Local Log In
- Single Sign-On (SSO)

Local Log in

User accounts using local authentication and LDAP will log in using this method.

1. Navigate to your ThreatQ instance - https://your-ThreatQ-web-ip-address.




- 2. Enter your username (email address) and password.
- 3. Optionally, if you have 2-step verification enabled, complete the following steps:
 - Enter your verification code from Google Authenticator.
 - Optionally, choose to **Remember this computer for 30 days**.
- 4. Click **Login** or **Submit**.

Single Sign-On (SSO)

Users using SAML authentication will use this log in method.



SAML users are required to add their email address to their user profiles in order to use the SSO. As part of the integration process, the ThreatQ platform expects that the user's email address has already been added to their IdP. See the Setting up LDAP Users/Groups for SAML topic for more details.



1. Navigate to your ThreatQ instance - https://your-ThreatQ-web-ip-address.

If SAML is enabled, you will see a Single Sign-On option.



2. Click on Log in Using SSO.

You will navigate to your third-party authenticated site to log in. Once that has been completed, you will be automatically sent back to the ThreatQ instance.



2-Step Verification

When you enable 2-Step Verification (also known as two-factor authentication), you add an extra layer of security to your account. After 2-Step Verification is active, you sign in with your password and a code sent to your mobile device.

The 2-Step Verification option is not available for users using SAML Authentication and the Single Sign-On (SSO) process.

Enabling 2-Step Verification

- 1. Click on your avatar icon, located to the top-right of the platform, and select **My Account**.
- 2. Under Enable 2-Step Verification, click **Enabled**.
- 3. In the Enable 2 Step Verification dialog box, complete the following:
 - a. Scan the qr code using your Google Authenticator mobile app.
 - b. Enter the validation code delivered to your mobile device via Google Authenticator.
 - c. Click Submit.
- 4. Click Save.

What to do next

The next time you log in, you must use the newest verification code.



Air Gapped Data Sync (AGDS)

Air Gapped Data Sync (AGDS) allows you to transfer data from a source ThreatQ installation to a target air-gapped ThreatQ installation. ThreatQ defines an air-gapped system as one that is not connected to a public network. This means that **external** feed ingestion will not occur on the air-gapped installation.

You should consult with ThreatQ Support or a Threat Intelligence Engineer prior to performing an Air Gapped Data Sync.

Air Gapped Data Sync consists of two synchronization commands:

- threatq:sync-export: the read command that copies data from the source ThreatQ installation
- **threatq:sync-import**: the write command that copies data to the target ThreatQ installation

If you are using LDAP or SAML authentication on your **Source** ThreatQ instance, and require users transferred via import to have authentication capabilities on your **Target** ThreatQ instance, then you must enable the same authentication method on your **Target** ThreatQ instance prior to performing import.

This section includes deployment details and configurations that should not be deviated from or changed without first consulting with ThreatQuotient. Any deviation of the ThreatQuotient recommended settings could result in system and platform instability, may render the system non-operational, and are not supported.

System Requirements

To use Air Gapped Data Sync, ThreatQ installations must meet the following requirements:

- ThreatQ v4.15 or later must be installed.
- All ThreatQ installations must run the same software version.
- All ThreatQ installations must be set to the correct time, time zone, and date, and using a clock source available to all. UTC is recommended.



Executing Air Gapped Data Sync

Using artisan commands at the command line of the ThreatQ installation, you execute air gapped data sync in two steps:

- 1. You run the **threatq:sync-export** command on the source ThreatQ installation; see Understanding threatq:sync-export.
- 2. You run the **threatq:sync-import** command on the target ThreatQ installation, see Understanding threatq:sync-import.

Running the threatq:sync-export Command

To run the threatq:sync-export command, complete the following steps:

- 1. SSH to your ThreatQ installation.
- 2. Navigate to the api directory using the following command:

```
<> cd /var/www/api
```

3. Run the following command appended by the necessary parameters, as described in Parameters: section of the threatq:sync-export topic.

```
<> sudo ./artisan threatq:sync-export
```

4. Review the Output and Sync report; see the Output and Sync Report section of the threatq:sync-export topic.

Running the threatq:sync-import Command

To run the threatq:sync-import command, complete the following steps:

- 1. SSH to your ThreatQ installation.
- 2. Navigate to the api directory using the following command:

```
<> cd /var/www/api
```



3. Run the following command appended by the necessary parameters:

```
<> sudo ./artisan threatq:sync-import
```

4. Review the Output and Sync report; see threatq sync-imprt File Output and Sync Report.



threatq:sync-import

The purpose of this command is to process the tarball of object data created by the threatq:sync-export command. Temporary sync tables are created on the target to house this object data, and integrity checks are run against existing data to verify IDs and check for duplicate objects. Duplicate objects from the source ThreatQ installation are updated, and new objects are inserted. The temporary sync tables are dropped when data processing is complete. Each run of this command also generates a sync report without output logs for the run.

Parameters

The following table outlines the parameters for the command. With the exception of --file, which is required, all parameters for the threatq: sync-import command are optional.

PARAMETER	EXPLANATION
file	File path to the tarball created by the threatq:sync-export command. This command is required to run the threatq:sync-import command.
	example:file=/tmp/tqSync-19-01-16-1547660837-8345.tar.gz
keep- created-at	Determines whether the oldest created_at date between the source and target ThreatQ installations should be maintained, or a new created_at is set on the target system. The default if this option is not provided by the user is for the oldest created_at date to be maintained. This value is required. Options are Y(es) or N(o). Default: Y example:keep-created-at=N
object-limit	Integer value used as the limit for the number of objects updated or inserted at a time. This value is required. When using this option, the size of the data sets on both source and target ThreatQ installations should be taken into account. Setting the limit too high may hinder performance. Default: 1000



PARAMETER	EXPLANATION
	example:object-limit=50000
memory- limit	Sets the PHP memory limit in Megabytes or Gigabytes. This value is required. Default: 2G example:memory-limit=4G
override- description	Determines whether or not the descriptions on existing objects on the target ThreatQ installation will be updated. If an existing object has a NULL description, it will be updated regardless of the use of this flag. Default: Y example:override-description=N

Examples

This command should be run from inside the /var/www/api directory.

Basic Run

```
<> sudo ./artisan threatq:sync-import
--file=/tmp/tqSync-19-01-16-1547660837-8345.tar.gz
```

This example will process all the data in the tarball provided in the --file option, using an object limit of 1000 for all inserts and updates. The created_at date of all transferred objects will be updated on the target ThreatQ installation if it is older than the current created_at date (if the object is already present on the source ThreatQ installation). Newly inserted objects will keep the created_at date of the source ThreatQ installation.

Set New created_at Dates on the Write System



```
<> sudo ./artisan threatq:sync-import
    --file=/tmp/tqSync-19-01-16-1547660837-8345.tar.gz
    --keep-created-at=N
```

This example will process all the data in the tarball provided in the --file option using an object limit of 1000 for all inserts and updates. The created_at date of all transferred will be left alone in the case of object updates, and to the current time in the case of new object inserts.

Increase the Object Limit

```
<> sudo ./artisan threatq:sync-import
    --file=/tmp/tqSync-19-01-16-1547660837-8345.tar.gz
    --object-limit=50000
```

This example will process all the data in the tarball provided in the --file option using an object limit of 50000 for all inserts and updates. The --keep-created-at option has been left out, so it will use the default setting of Y(es) and created_at dates will be maintained from the read system.

Initial Setup

You **must** run the threatq:fill-sync-hash-column command, before running the threatq:sync-import command on an air gapped ThreatQ installation. This command prepares the database of an air gapped installation to run the threatq:sync-import command. Upon upgrade to ThreatQ version 4.17 and later, several tables will include a sync_hash column, which stores an MD5 hash of the unique fields for records in each table. This command fills in the data in this column, before attempting an Air Gapped Data Sync import. Data added after upgrade will automatically have their sync_hash columns populated on insert and update, so it is only necessary to run this command once.

The threatq:sync-import command checks for any NULL values in the sync_hash column in the events, indicators, and object_links tables before importing any data, and will fail if any NULL values are found. If the threatq:fill-sync-hash-column command is not run and sync_hash columns are found on the indicators, events, or object_links tables, the import will fail and ask you to run the command to fill that column before continuing.

Running the threatq:fill-sync-hash-column Command

- 1. SSH to your target ThreatQ installation.
- 2. Change directories to /var/www/api.



- 3. Run php artisan down to place ThreatQ into maintenance mode.
- 4. Run the following command:

```
sudo ./artisan threatq:fill-sync-hash-column
```

5. Run php artisan up to bring ThreatQ out of maintenance mode.

Run Scenarios

Success

When a run of this command completes successfully, a report will appear in the directory the command was run in (/var/www/api). There will also be a record in the database synchronizations table for the run. Both of these will contain data describing performance metrics and object counts.

Excluded Files

If the --ignore-file-types option was used during creation of the export tarball, then the physical files associated with File objects that have the File Types specified in that option will not be available during the import of those objects. If the import command detects that a file is missing from the export tarball, it will create a placeholder file under the same file path as was set on the read box (this is defined in the path field of the File). This placeholder file will be a simple text file with the phrase "File excluded from export.". Please be aware that because the original physical file associated to the File object has been replaced, it will no longer be possible to open the physical file on the Details page for that File object.

Errors

If a run of this command fails before completion, error messages will not appear in the report file - though they will appear in the laravel log and in the console. There is not currently a means of restarting the command from where it left off. The command will need to be restarted and will run through all the data again. Any data from the tarball that was written during the previous failed run will simply be updated (rather than inserted again), meaning the end result will be the same - all data will be transferred from the tarball to the target system.

Data Processing

Data found in CSV dump files for a table from the tarball provided in the --file option is inserted into a corresponding sync table. A sync table is just a copy of a base table, with column structure maintained but indexes excluded. Indexes are added to unique columns on



sync tables (which will later be used in table joins and where clauses) once data insertion from dump files is complete, since indexes slow the insertion process down.

The naming convention for a sync table is sync_import_<base table name>_process id>.



Base table: adversaries

Sync table: sync_import_adversaries_12345

All sync tables are removed from the target ThreatQ installation's database once data processing is complete.

Basic Table

A basic table has no foreign keys pointing to other tables in the database. It has a single identifier (id) column for each record. Once all the data stored in the tarball for a basic table has been transferred to a sync table, the sync table has an <code>existing_id</code> column added with a default value of NULL for each record. This column is used to determine whether the record already exists on the target ThreatQ installation. The id for the record on the target system may be different from that of the record from the source ThreatQ installation, so this <code>existing_id</code> column ensures that data integrity is maintained between the two.

Sample Basic Table:

attachment_types - (id, name, is_parsable, parser_class, created_at, updated_at, deleted_at)

Sample Sync Table created from Basic Table:

sync_import_attachment_types_12345 - (existing_id, id, name, is_parsable, parser_class, created_at, updated_at, deleted_at)

Tables with Pivots

A pivot table has one or more foreign keys pointing to other tables in the database. Once all the data stored in the tarball for a table with pivots has been transferred to a sync table, the sync table has an existing_<pivot>_id column added for each foreign key column, as well as an existing_id column for the record itself (all set to a default value of NULL).



File Output

threatq sync-import File Output and Sync Report

Once all data has been processed, a Sync Report will be generated in the /var/www/api directory (where the command is run). This file will be named after the tarball used in the run, with the extension "-sync-import.txt"



Tarball used: tqSync-19-01-16-1547660837-8345.tar.gz

Sync Report name: tqSync-19-01-16-1547660837-8345-sync-import.txt

threatq:sync-import Command Line Output

Command line output displays command progress and object totals. It will be similar to the output in the Sync Report.

Synchronizations

Table

synchronizations

- id The auto-incremented id for the Synchronization record
- type The Synchronization direction (options are "export" or "import")
- started at The date and time the command run was started
- finished_at The date and time the command run completed
- config_json A JSON representation of the command run configuration
- report_json A JSON representation of the command run parameters (command line options, object counts, tables created, etc)
- pid The process id of the command run
- hash Unique identifier for a command run (md5 hash of the config_json column)
- created_at The date and time the Synchronization record was created
- updated_at The date and time the Synchronization record was updated



Record Handling

Hash

The Synchronization record hash column is automatically calculated as an md5 of the config_json column on record creation.

Initial Creation

A Synchronization record is created at the beginning of a command run, right after all command line options have been processed. Initial creation only covers the type, started_at, pid, and config_json columns. For this command (threatq:sync-import), the type will be "import". The command line option portion of the report_json is added as well, but this column will not be complete until the record is finalized. The finished_at column remains NULL.

Finalization

A Synchronization record is finalized when the command run has completed. At this time, the finished_at column is filled with the completion date and time, and the report_json column is updated to include information about the run (object counts, tables created, etc).



threatq:sync-export

The purpose of this command is to pull all objects, object context, tags, and object links from the source ThreatQ installation and then store them in CSV data dump files. You can specify which objects are pulled, based on a date or via configuration. All data pulled into the CSV data dump files can then be transferred to a target air-gapped ThreatQ installation for validation and import. Each run of this command also generates a sync report with output logs for the run.

Parameters

DADALACTED

The following table outlines the parameters for the command. All parameters for the threatq: sync-export command are optional. If you do not set any parameters, the system runs a default configuration as explained in threatq:sync-export Configuration.

EVEL ANIATION

PARAMETER	EXPLANATION
target	Target directory where the output file should be placed. This value is required.
	Default: /tmp
	example:target=/my/directory
start-date	The start date for data selection. This value is required.
	ex:start-date="2018-01-01 00:00:00"
end-date	The end date for data selection. This value is required. Applies only to objects themselves, not object context or object links.
	example:end-date="2018-01-02 00:00:00"
include- deleted	Determines whether objects that have been soft-deleted are included in the result set. Options are Y(es) or N(o).
	Default: N



PARAMETER	EXPLANATION
	example:include-deleted=Y
include- investigations	Determines whether Investigations and Tasks are included in the result set. This value is required. Options are Y(es) or N(o). Default: N
	example:include-investigations=N
meta-only	If present, tells the command to only include meta data (no object data) in the result set. No value necessary.
memory-limit	Sets the PHP memory limit in Megabytes or Gigabytes. This value is required. Default: 2G
	example:memory-limit=4G
object-limit	Sets the limit on the number of objects selected at a time. Recommended use is to set the limit to a number smaller than the default (50,000) on boxes with very large data sets. Default: 50,000 example:object-limit=10000
ignore-file- types	Defines a comma-delimited list of ThreatQ File Types for which physical files stored on the source ThreatQ installation should not be transferred to the target air-gapped ThreatQ installation. Database records are still included in the export tarball.
	xample:ignore-file-types="Malware Analysis Report"
	example:ignore-file-types="Malware Analysis Report,Malware Sample"



Examples

This command should be run from inside the /var/www/api directory. The following examples provide use cases for air gapped data sync.

No Time Limit, Default Configuration

```
<> sudo ./artisan threatq:sync-export
```

This example will pull all objects in the system (with the exception of Investigations, Tasks, and soft-deleted Objects). The output will appear in /tmp.

Meta Data Only

```
<> sudo ./artisan threatq:sync-export --meta-only
```

This example will pull only meta data objects from the system (Attributes, Sources, Object Statuses and Types, and so on).

Time Limit

```
<> sudo ./artisan threatq:sync-export --start-date
="2018-10-01 00:00:00" --end-date="2018-11-01 00:00:00"
```

This example will pull objects whose updated_at or touched_at occurs between the start and end date.

Exclude Malware Files

```
<> sudo ./artisan threatq:sync-export --ignore-file-types="Malware
Sample"
```

This example will pull all objects, but will exclude the physical files attached to any File objects with the type Malware Sample. The File objects themselves (as well as their context and relationships) will still be included in the export tarball.

Any File Type can be used with this option, and multiple File Types can be included as a comma-delimited list.



```
<> sudo ./artisan threatq:sync-export --ignore-file-
types="STIX,PDF,Malware Sample"
```

Cron Configuration

```
<> sudo ./artisan threatq:sync-export
   --target=/my/directory --include-deleted=Y
   --include-investigations=N
```

This example will do a search for a previous synchronization record with the same hash (comprised of the three options provided). If any hash matches are found, the run will use the started_at date of the most recent previous record as the start date for the current run.

If you do not require soft-deleted Objects, Investigations, or Tasks to be transferred to the target ThreatQ installation, then only the --target option is necessary (as the defaults for the other two options are both (N)o).

Initial Cron for First Time Use

Determine what the cron configuration options should be:

- target directory
- · whether investigations/tasks should be included
- whether deleted objects should be included

The cron configuration options must be the same for every run, but they only need to be specified if different from the defaults.

Run the command with the cron configuration options:

```
<> php artisan threatq:sync-export
    --target=/my/directory --include-investigations=Y
    --include-deleted=N
```

Instructions for Larger Data Sets (Starting from the Beginning of Time)

For larger data sets, it is undesirable to do a full run from the beginning of time (performance will suffer).





ThreatQuotient recommends that you use the --end-date option to specify an upper limit on the date range pulled. Multiple runs will be necessary to process all data up to the current date.

Determine what the cron configuration options should be:

- target directory
- · whether investigations/tasks should be included
- whether deleted objects should be included

The cron configuration options will need to be the same for every run, but they only need to be specified if different from the defaults.

For each of the runs, provide the configuration options along with the --end-date option:

```
<> php artisan threatq:sync-export
    --target=/my/directory --include-investigations=Y
    --end-date="2017-01-01 00:00:00"
```

Once the current date has been reached, the --end-date option will no longer be necessary.

Instructions for Larger Data Sets (Starting from a Specified Date)

For larger data sets, it is undesirable to do a full run from the beginning of time (performance will suffer).



ThreatQuotient recommends that you use the --end-date option to specify an upper limit on the date range pulled. Multiple runs will be necessary to process all data up to the current date.

If only a subset of data needs to be processed up to the current date, then you should use the --initial-start-date option.

Determine what the cron configuration options should be:

- target directory
- whether investigations/tasks should be included
- whether deleted objects should be included



The cron configuration options will need to be the same for every run, but they only need to be specified if different from the defaults.

For the first run, provide the configuration options along with the --initial-start-date option.

```
<> php artisan threatq:sync-export
    --initial-start-date="2017-01-01 00:00:00" --target=/my/directory
    --include-investigations=Y --end-date="2017-02-01 00:00:00"
```

For each of the runs, provide the configuration options along with the --end-date option:

```
<> php artisan threatq:sync-export
    --target=/my/directory --include-investigations=Y
    --end-date="2017-01-01 00:00:00"
```

Once the current date has been reached, the --end-date option will no longer be necessary.

Run Scenarios

Success

When a run of this command completes successfully, a tarball of data will appear in the target directory you specified (or /tmp by default). A report file describing the run will be available in the data tarball, under the /sync directory. There will also be a record in the database synchronizations table for the run.

Errors

If a run of this command fails before completion, the tarball will not be created. There will be a data directory in the target directory (where the data is stored before it is compressed) that contains all the data that was processed before the failure. The report file will appear in this directory under /sync. Error messages will not appear in the report file - though they will appear in the laravel log and in the console.

Regardless of whether the run was part of a cron configuration, it can simply be restarted. The cron configuration will look for the last completed run to find the next start date.

Dates

Start Date



A start date is applied to objects according to the column available - touched_at or updated_at.

touched_at Objects

Adversaries, Attachments, Events, Indicators, Signatures, Custom Objects

updated_at Objects

Investigations, Tasks, Object Links, Tagged Objects

End Date

An end date is applied only if you provide one at run time. It is applied everywhere a start date is used.

Configuration

The configuration used for each run of this command consists of the --target, -include_deleted, and --include_investigations command line options and is stored in the
config_json column of the Synchronization record. The hash column of each Synchronization
record is a md5 hash of the config_json column.

Default

The default configuration is used if the command is run with no options provided:

- target_directory = /tmp
- include_deleted = false
- include_investigations = false

In this configuration, the initial run start date will default to 1970-01-01 00:00:00.

Cron

If the command is run with the --target, --include_deleted, and --include_investigations parameters, the hash of these values will be compared against the hash column of previous runs. Using these three options on every run allows for the command to be incorporated into a scheduled task.

If any hash matches are found, the start date for the run will be set to the started_at date in the Synchronization record of the previous run with the same hash.



If no hash matches are found, the start date will be set to 1970-01-01 00:00:00.

Start Date Provided

If a start date is included in the command run using the --start-date option, any other options also provided will be honored. However, if the --target, --include_deleted and --include_investigations options are also included, a Cron check against the hash of these three options will **not** occur. The start date provided will be included in config_json as the **manual_start_date** so that the run does not collide with any Cron-related runs.

If a "beginning of time" run is necessary, use the option as --start-date="1970-01-01 00:00:00".

Output and Sync Report

The following sections detail the data you may find in the export output and sync report.

Meta Data

Meta data is transferred with every run of this command by default. You can specify that only meta data (no object data) should be pulled in a run by using the --meta-only option.

Meta data includes information about Sources, Attributes, Tags, as well as Object Statuses and Types (both seeded and user-provided).

While meta data like Connectors and Operations are included in this list, they are not installed on the target ThreatQ installation as part of the air gapped data sync process. They are only placed in the requisite tables for use as Sources of Objects that are transferred. The same is true of any Users that are copied - these will not be enabled Users on the target installation; they will be transferred as disabled.

Meta Data Objects

- Attributes
- Clients
- Connectors
- Connector Categories
- Connector Definitions



- Content Types
- Groups
- Investigation Priorities
- <Object Type> Statuses
- <Object Type> Types
- Other Sources
- Operations
- Sources
- Tags
- TLP
- Users

Objects

This command covers any objects installed on the system by default, and any custom objects that have been installed by the user. The only objects that can be excluded are Investigations and Tasks (using the --include-investigations command line option).



Custom Objects that are installed on a source ThreatQ installation that have NOT been installed on a target ThreatQ installation will NOT be installed by the air gapped data sync process. If an object is included in the export data, but is not found on the target, it will be ignored.

Default Objects:

- Adversaries
- Attachments (Files)
- Events
- Indicators
- Signatures
- Campaigns
- · Courses of Action
- Exploit Targets
- Incidents
- TTPs



Storage:

The data for each object is copied as a dump file in CSV format using "SELECT * INTO OUTFILE..." MariaDB syntax. The full query for the data is built up using the options you provided (start date, end date, etc).

Dump files contain a maximum object limit of 50,000 (set in the Synchronization base class). Dump files are created (with a counter appended to the file name) until the entire object result has been covered.

To ensure that any Objects present in Object Context (Attributes, Comments, and Sources), Object Links, Tagged Objects, or Investigation Timeline Objects are also included in the base Object data, CSV dump files for each Object type are also created from queries against each of these tables. This is necessary because of the differing date columns used in each query (an object may appear in an Object Link in the specified date range according to the Object Link's updated_at date, even though the Objects themselves saw no change to their touched_at date in that date range). When the data from all of these object files is transferred to the target ThreatQ installation, any duplicates across dump files will be consolidated. Files that contain Object data will always include "_obj_" in the file title.

Sample Object File List (all of these files will contain Adversary records):

- adversaries/adversaries_obj_0.csv
- adversaries/adversaries_obj_attributes_0.csv
- adversaries/adversaries_obj_comments_0.csv
- adversaries/adversaries_obj_investigation_timelines_0.csv
- adversaries/adversaries_obj_object_links_dest_0.csv
- adversaries/adversaries_obj_object_links_src_0.csv
- adversaries/adversaries_obj_sources_0.csv
- adversaries/adversaries_obj_tags_0.csv

Object Context

The date range for queries on Object Context tables uses the updated_at date column, with the exception of Adversary Descriptions, which uses the created_at date column.



Adversary Descriptions are handled as part of the Object Context gathering process. The adversary_descriptions table is queried using the created_at date column, and the entirety of the adversary_description_values table is pulled, as it doesn't have a date column.

Not all Objects have all Object Contexts (Attributes, Attribute Sources, Comments, and Sources). Tables are only polled if they exist.

Tables Covered for each Object Type:

- <object type>_attributes
- <object type> attribute sources
- <object type>_comments
- <object type>_sources

Sample Object Context File List (Indicator Object Type):

- indicators/indicator_attribute_sources_0.csv
- indicators/indicator_attributes_0.csv
- indicators/indicator_comments_0.csv
- indicators/indicator_sources_0.csv

Other Data

Attachment Files

Physical files for all attachments included in the date range are copied into the attachments/ files directory of the data tarball.

Object Links

The date range for queries on Object Links uses the updated_at date column.

Tables Covered (Object Links and Object Link Context):

- object_links
- object_link_attributes
- object_link_attribute_sources
- object_link_comments
- object_link_sources



Sample Object Link File List:

- object_links/object_links_0.csv
- object_links/object_link_attributes_0.csv
- object_links/object_link_attribute_sources_0.csv
- object_links/object_link_comments_0.csv
- · object links/object link sources 0.csv

Tags

The date range for queries on Tagged Objects uses the updated_at date column.

Tables Covered (Tags themselves are covered in the Meta Data):

tagged_objects

Sample Tagged Objects File List:

tagged_objects/tagged_objects_0.csv

Spearphish

The date range for queries on Spearphish uses the updated_at date column.

Tables Covered:

spearphish

Sample Spearphish File List (Spearphish files are stored with Event data):

events/spearphish_0.csv

Investigations

The date range for queries on additional Investigation context tables uses the updated_at column.

Tables Covered:

- investigation_nodes
- investigation_node_properties
- investigation_timelines



- investigation_timeline_objects
- investigation_viewpoints

Sample Investigation additional context File List:

- investigations/investigation_node_properties_0.csv
- investigations/investigation_nodes_0.csv
- investigations/investigation_timeline_objects_0.csv
- investigations/investigation_timelines_0.csv
- investigations/investigation_viewpoints_0.csv

File Output

Data Tarball

Once all data has been processed, a tarball is created containing all output files. This tarball will be dropped in the directory specified in the --target option, or the /tmp directory by default.

Tarball Naming Convention: tqsync_<run date>.tar.gz



tqSync-19-01-16-1547649934-0849.tar.gz

Sync Report

The output for each run is stored in a Sync Report output file, which is located in the sync directory of the data tarball. The file is always named sync-export.txt.

Command Line Output

Command line output displays command progress, object totals, and files written.

Synchronizations

Table



synchronizations

- id The auto-incremented id for the Synchronization record
- type The Synchronization direction (options are "export" or "import")
- started_at The date and time the command run was started
- finished_at The date and time the command run completed
- config_json A JSON representation of the command run configuration
- report_json A JSON representation of the command run parameters (command line options, object counts, files created, etc)
- pid The process id of the command run
- hash Unique identifier for a command run (md5 hash of the config_json column)
- created_at The date and time the Synchronization record was created
- updated_at The date and time the Synchronization record was updated

Record Handling

Hash

The Synchronization record hash column is automatically calculated as an md5 of the config_json column on record creation.

Initial Creation

A Synchronization record is created at the beginning of a command run, right after all command line options have been processed. Initial creation only covers the type, started_at, pid, and config_json columns. For this command (threatq:sync-export), the type will be "export". The command line option portion of the report_json is added as well, but this column will not be complete until the record is finalized. The finished_at column remains NULL.

Finalization

A Synchronization record is finalized when the command run has completed. At this time, the finished_at column is filled with the completion datetime, and the report_json column is updated to include information about the run (object counts, files created, etc).




Upgrading an Air Gapped ThreatQ Instance



Contact ThreatQ Support if you encounter any issues during the upgrade or require assistance.

- Log into the ThreatQ download repository, https://download.threatq.com, using your YUM credentials.
- 2. Locate and download the appropriate airgap upgrade file.



3. Open the CLI of the device to upgrade and run the following:

```
<> mkdir /var/tmp/upgrade
```

- 4. Copy the upgrade file you downloaded in step 2 to the newly created directory /var/tmp/upgrade using the scp client of your choice.
- 5. Return to the CLI of the device and confirm that the upgrade file is present.
- 6. Use the following commands to unpack and run the upgrade file:

```
<> sudo su -
   screen -S threatq
   cd /var/tmp/upgrade
   ls -al
   tar -xzvf /var/tmp/upgrade/<upgrade filename>
   /var/tmp/upgrade.sh
```



7. Allow the upgrade process to complete. When complete, the output should resemble the following:

```
Installed:
  chrony.x86_64 0:3.2-2.el7
  device-mapper-event.x86_64 7:1.02.149-10.el7_6.7
  device-mapper-event-libs.x86_64 7:1.02.149-10.el7_6.7
 device-mapper-persistent-data.x86_64 0:0.7.3-3.el7 dnsmasq.x86_64 0:2.76-7.el7
  gnutls.x86_64 0:3.3.29-9.el7_6
  gsettings-desktop-schemas.x86_64 0:3.28.0-2.el7
  libXfont.x86_64 0:1.5.4-1.el7
  libgnome-keyring.x86_64 0:3.12.0-1.el7
libgudev1.x86_64 0:219-62.el7_6.6
  libldb.x86_64 0:1.3.4-1.el7
  librabbitmq-devel.x86_64 0:0.8.0-2.el7
  libtalloc.x86_64 0:2.1.13-1.el7
  libtdb.x86_64 0:1.3.15-1.el7
libtevent.x86_64 0:0.9.36-1.el7
  libtirpc.x86_64 0:0.2.4-0.15.el7
libzip-last.x86_64 0:1.1.3-1.el7.remi
  lm_sensors.x86_64 0:3.4.0-6.20160601gitf9185e5.el7
 lvm2.x86_64 7:2.02.180-10.el7_6.7
lvm2.x86_64 7:2.02.180-10.el7_6.7
lvm2-libs.x86_64 7:2.02.180-10.el7_6.7
mlocate.x86_64 0:0.26-8.el7
  net-snmp-libs.x86_64 1:5.7.2-37.el7
  net-snmp-utils.x86_64 1:5.7.2-37.el7
nettle.x86_64 0:2.7.1-8.el7
  postgresql-libs.x86_64 0:9.2.24-1.el7_5
  python-markdown.noarch 0:2.4.1-2.el7
  rpcbind.x86_64 0:0.2.0-47.el7
  samba-common.noarch 0:4.8.3-4.el7
  trousers.x86_64 0:0.3.14-2.el7
Complete!
[root@support02 upgrade]#
[root@support02 upgrade]#
root@support02 upgrade]#
```

If your terminal session should end prematurely at any point during the upgrade, you can return to it by logging back into the CLI and running the command below.

<> screen -r threatq



Backup and Restore

The following describes how to back up and restore a ThreatQ instance.

ThreatQ Backup

Before performing a backup of a ThreatQ instance, note the following:

- The backup process stops and starts all ThreatQ services automatically in order to prevent modifications to the file system and database. Requests made during this time are queued and resumed once the backup process completes.
- The time it takes to back up ThreatQ depends primarily on the size of the database. For this reason, we recommend performing a backup when system availability is not critical, such as during a scheduled maintenance window.
- The resulting backup file can be large. We recommend that you write it to a mounted drive or file location rather than the local file system. For instructions on how to mount a network-available drive, contact ThreatQ Support. If the backup file must be stored locally, you should move it off the local file system at the earliest opportunity.
- By default, the system creates a backup of the threat intelligence data index required for improved search performance and includes it in the backup file. This operation may take hours. You can omit this portion of the backup by running the backup command with the --exclude-solr option. However, this means that your threat intelligence data must be re-indexed during or after the restore process.

To perform a ThreatQ backup:

- 1. SSH to the ThreatQ command line and elevate your user privilege to root or sudo.
- 2. Change the directory to /var/www/api.
- 3. Choose one of the following options:
 - To create a backup that includes a Threat Library re-index, run the following command:

```
<> sudo php artisan threatq:backup
```

 To create a backup that excludes a Threat Library re-index, run the following command:

sudo php artisan threatq:backup --exclude-solr



4. When prompted, provide the **root mysql** password you configured during first boot.

You will only be prompted for a password and file path with the first initial backup. You will not be prompted for either of these items for any subsequent backups. Contact ThreatQ Support if you need to update either of these items.

5. Provide the path to the file location where you want to create the backup.

The script generates a backup file in the specified file location. The name of the file will be **threatq_backup_x.x.x_yyyy-mm-dd.tgz**, where **x.x.x** is the TQ version and **yyyy-mm-dd** is the date when the backup was performed.

ThreatQ Restore

To restore from a ThreatQ backup, note the following:

- The target machine must be an existing ThreatQ instance running the same version of the instance captured in the backup.
- The restore process completely overwrites the current installation.
- The backup file needs to be accessible by the target ThreatQ instance, either locally or on a mounted drive.
- The backup file will be unzipped in the same directory where it resides. Ensure that the available disk has sufficient space to hold both the backup archive and the extracted directory. The extracted directory can be removed after the restore is complete.
- Depending on the size of the instance being restored, the process can take a while.
- The machine running the target ThreatQ instance automatically restarts once the restore process is complete.

To restore from a ThreatQ backup, perform the following procedure on the target ThreatQ instance.

- 1. Complete the first boot process on the new host by navigating to its IP address in a web browser and entering your credentials. If this step is not completed, the remaining steps are not successful.
- 2. SSH to the command line and elevate your user privileges to root or sudo.
- 3. Verify that you have the necessary utilities in place by running: **yum install policycoreutils-python-2.2.5-20.el7.x86_64**.
- 4. Change directory to /var/www/api.
- 5. Issue the following commands:



```
<> php artisan threatq:restore </path/to/backup_file>
    php artisan threatq:update-events
```

- 6. When prompted, provide the root mysql password you configured during first boot.
- 7. If the backup file does not include the intelligence data index required for improved search performance, the system prompts you to either allow an automatic re-index or manually perform it later.
 - This operation may take hours.
- 8. After the restore completes, you should reboot the target ThreatQ system to ensure that the system processes start up correctly.



Command Line Interface (CLI)

You can use the CLI to perform tasks and initiate specific platform processes.

Important Notes

- You should SSH into your ThreatQ installation as root or have sudo permission.
- Some CLI commands require you to be in a specific directory to execute. Review the help center topic for each command before running.
- Most CLI commands require that the ThreatQ application be placed into maintenance mode before proceeding. Placing the application in maintenance mode allows you to perform operations which would be delayed or otherwise impeded by regular API operation. Review the Maintenance Mode section below before executing CLI commands.

Maintenance Mode

Command Line Interface (CLI) commands and other processes, such as backup and restore, require that you place the ThreatQ application into maintenance mode. Placing the application in maintenance mode allows you to perform operations which would be delayed or otherwise impeded by regular API operation.

Some CLI commands will automatically place the ThreatQ application into maintenance mode when executed. The help center topics for these commands will indicate if the command will automatically place the ThreatQ application into maintenance mode.

Placing the ThreatQ Application into Maintenance Mode

- 1. SSH to your ThreatQ installation.
- 2. Navigate to the api directory using the following command:
 - <> cd /var/www/api
- 3. Run the following command:
 - <> sudo php artisan down



The platform will now be in maintenance mode. [root@techpubstq api]# php artisan down Application is now in maintenance mode.

[root@techpubstq api]#

Taking the ThreatQ Application out of Maintenance Mode



The following steps assume you are already in the CLI. If not, complete steps 1-2 from above before proceeding.

1. While under the /var/www/api directory, run the following command:

<> sudo php artisan up

The platform will now be out of maintenance mode.

[[root@techpubstq api]# php artisan up Application is now live. [root@techpubstq api]#



Commands

This topic contains a list of useful CLI commands.

Auto Configuration MariaDB Command

The Auto Configuration MariaDB command will execute a script that will update your MariaDB configurations based on your available system resources. The script is executed automatically during the platform install/upgrade process but can executed manually by using the command below. You will typically use this command after making a change to the size of your ThreatQ instance or system memory.



MariaDB will need to be restarted after the script has completed its updates.

<> /etc/my.cnf.d/config_gen/mysql_config_generator

System ThreatQ Purge



Read this section carefully before running the ThreatQ Purge Command. After running this command, your threat intelligence data cannot be recovered.

The ThreatQ Purge command will **permanently** delete all object-related threat intelligence data from your ThreatQ installation, including audit logs. It will maintain any configuration-related settings, such as expiration, scoring, and so on.

Running the ThreatQ Purge Command

The ThreatQ Purge command will **permanently** delete all object-related threat intelligence data from your ThreatQ installation, including audit logs. It will maintain any configuration-related settings, such as expiration, scoring, and so on.

- 1. SSH to your ThreatQ installation.
- 2. Navigate to the api directory using the following command:

<> cd /var/www/api



- 3. Place the application into maintenance mode see the Maintenance Mode section.
- 4. Run the following command:

```
<> sudo php artisan threatq:purge-threat-intelligence
```

5. You will be presented the following prompt:

```
<> You are about to erase all of your data, are you sure?
```

- 6. Enter Yes or No.
- 7. Bring the application out of maintenance mode see the Maintenance Mode section.

Add/Upgrade CDF

Use the steps below to add or upgrade a Configuration Driven Feed (CDF) using the Command Line Interface (CLI). The command creates connectors for each feed defined in the feed definition file.

To install a CDF:

- 1. SSH to your ThreatQ installation.
- 2. Navigate to the api directory using the following command:

```
<> cd /var/www/api
```

- 3. Place the application into maintenance mode see the Maintenance Mode section.
- 4. Run the following command:

```
<> sudo php artisan threatq:feed-install <Feed Definition File>
```



The application will notify you if the feed(s) in the feed definition file already exists in the system and will cancel the installation. See the **To Upgrade a CDF**



and **Changes in User Configurations** sections below for more information.

threatq:feed-install 6266 Started > 2019-02-21 18:47:24 threatq:feed-install 6266 Command failed: The provided definition file contains the following installed feeds: Testing at 5 AM. Proceed with the update by using the --upgrade flag.

5. Bring the application out of maintenance mode - see the Maintenance Mode section.

To Upgrade a CDF

This command can be used to update a feed's Category and Namespace. If the category exists on the appliance, the command will update both fields and link the feed to the designated category. ThreatQ will confirm that the defined category exists before completing the update command. If the category does not exist, ThreatQ will not update the feed.

- 1. SSH to your ThreatQ installation.
- 2. Navigate to the api directory using the following command:

```
<> cd /var/www/api
```

- 3. Place the application into maintenance mode see the Maintenance Mode section.
- 4. Run the following command:

```
<> sudo php artisan threatq:feed-install <Feed Definition File>
   --upgrade
```

5. Bring the application out of maintenance mode - see the Maintenance Mode section.

Changes in User Configurations

When upgrading an existing feed using the --upgrade flag, the application will compare the existing version of the feed with the new version for differences in the user configuration. If a difference is detected, the application will inform you that the current user configuration for that feed will be overwritten. The application will require user input to continue with the feed upgrade.

```
threatq:feed-install 6266 Started > 2019-02-21 18:47:24 threatq:feed-install 6266 Command failed: The provided definition file contains the following installed feeds: Testing at 5 AM. Proceed with the update by using the --upgrade flag.
```



It is recommended that you create a copy of the existing configuration values before proceeding with the upgrade.

Command Flag Help

You can also see a full list of command flags using the following command while under the / var/www/api directory:

```
<> sudo php artisan threatq:feed-install --help
```

Source Consolidation

Use the steps below to consolidate/deduplicate similarly named sources and to remove unused sources from the ThreatQ application. A source that have been removed or merged will have its data mapped to a new source.

The command does not require recalculation of scoring.

- 1. SSH to your ThreatQ installation.
- 2. Navigate to the api directory using the following command:

```
<> cd /var/www/api
```

- 3. Place the application into maintenance mode see the Maintenance Mode topic.
- 4. Run the following command:

```
<> sudo php artisan threatq:consolidate-sources
```

5. Bring the application out of maintenance mode - see the Maintenance Mode topic.

Example Scenario:

- 1. User manually adds ABC as a source.
- 2. User enables ABC.

There are now two ABC sources in the system.

3. User runs consolidation command.



4. The application merges the sources and remaps any items linked to the correct source.

Source Merge

Use the steps below to merge a user-created source (source origin) with another source (source destination). After merging, the source origin will be deleted and source changes will be reflected in the Audit log (Example: Source A become Source B).

The command does not affect date stamps nor does it require a recalculation of scoring.

- 1. SSH to your ThreatQ installation.
- 2. Navigate to the api directory using the following command:

```
<> cd /var/www/api
```

- 3. Place the application into maintenance mode see the Maintenance Mode section.
- 4. Run the following command:

```
<> sudo php artisan threatq:merge-sources --origin-
source="<source a>" --destination-source="<source b>"
```

5. Bring the application out of maintenance mode - see the Maintenance Mode section.

Example Scenarios:

SCENARIO DETAILS

Merge user-created source (origin source) with a system source (destination source).

- 1. User places the platform into maintenance mode.
- 2. User runs Source Merge command.
- 3. User is presented with merge confirmation dialog.
- 4. User consents to the merge.



SCENARIO DETAILS

- 5. The platform will merge the origin source into the destination source and then delete the origin source after completion.
- 6. The platform will record the source merge in the audit log for affected data.
- 7. The user receives a command success message.
- 8. The user brings the platform out of maintenance mode.

Merge system source (origin source) with a user-created source (destination source).

- 1. User places the platform into maintenance mode.
- 2. User runs Source Merge command.
- 3. The platform will inform the user that a system source cannot be merged into another source.
- 4. The user brings the platform out of maintenance mode.

Merge user-created source (origin source) with a system source (destination source) with duplicate records.

- 1. User places the platform into maintenance mode.
- 2. User runs Source Merge command.
- 3. The platform will inform the user that there are duplicate records between the two sources and prompt the user to run the Source Consolidation command before proceeding with the merge.
- 4. User runs the Source Consolidation command.
- 5. User runs Source Merge command.
- 6. User is presented with merge confirmation dialog.
- 7. User consents to the merge.
- 8. The platform will merge the origin source into the destination source and then delete the origin source after completion.



SCENARIO DETAILS

- 9. The platform will record the source merge in the audit log for affected data.
- 10. The user receives a command success message.
- 11. The user brings the platform out of maintenance mode.

Merge user-created source (origin source) with a system source (destination source) with an assigned TLP.

- 1. User places the platform into maintenance mode.
- 2. User runs Source Merge command.
- 3. User is presented with merge confirmation dialog.
- 4. User consents to the merge.
- 5. The platform will merge the origin source into the destination source, and then delete the origin source after completion.
- 6. The platform will then apply the destination source's default TLP settings to the merged data and record the source merge in the audit log for affected data.
- 7. The user receives a command success message.
- 8. The user brings the platform out of maintenance mode.

Historic Pull

If not called out specifically in Historic Feed Pulls, use the following commands at the command line to run historic pulls for most other connectors, including most TAXII feeds.

1. Run the following command to determine the feed name (\$FEEDNAME):

<> tqconnector -h

Take note of the desired feed name.



2. Run the following command to run the historic pull, substituting your desired start and end date:

```
<> sudo -u threatq tqconnector -f $FEEDNAME -s MM-DD-YYYY -e MM-
DD-YYYY
```

Merge Attributes

The Merge Attributes command allows you to merge an existing attribute to a new or different existing attribute name. This is useful in the case that an attribute key is outdated or entered incorrectly.



If the MERGE-NAME attribute in the command does not exist, it will be automatically created upon executing the command.

You can also filter the command to only merge attributes that have a specific source(s) using an optional --source argument. If the source identified in the command does not exist, or the argument is not included, the command will merge all OLD-NAME attributes into MERGE-Name.

- 1. SSH to your ThreatQ installation.
- 2. Navigate to the api directory using the following command:

```
<> cd /var/www/api
```

- 3. Place the application into maintenance mode see the Maintenance Mode topic.
- 4. Run the following command:

```
<> sudo threatq:merge-attributes --old-name='OLD-NAME' --merge-
name='MERGE-NAME' --source='SOURCE'
```



The --source argument is optional. You can omit this parameter in order to target all attributes with the OLD-NAME.

5. Bring the application out of maintenance mode - see the Maintenance Mode topic.

Example - Merge Attribute without using --source option





sudo threatq:merge-attributes --old-name='Cuontry' --merge-name='Country'

In the example above, the attribute cuontry would be merged into the country attribute. So if you have an any instance of this attribute name (with value), cuontry: us, on an object, after running the command, the attribute value would appear as country: us on that object.

Example - Merge Attribute using --source option



sudo threatq:merge-attributes --old-name='Cuontry' --merge-name='Country' -source='CrowdStrike'

In the example above, the attribute cuontry, if it has a source of crowdstrike, would be merged into the country attribute. So if you have an instance of this attribute name (with value), cuontry: us, on an object, after running the command, the attribute value would appear as country: us on that object.

Example - Merge Attribute using --source option (multiple sources)



sudo threatq:merge-attributes --old-name='Cuontry' --merge-name='Country' -source='CrowdStrike' --source='McAfee ATD'

In the example above, the attribute cuontry, if it has a source of crowdstrike or McAfee ATD, would be merged into the country attribute. So if you have an instance of this attribute name (with value), cuontry: us, on an object, after running the command, the attribute value would appear as country: us on that object.

iSight Historic Pull

To run an iSight historic pull, run the following command from the command line, substituting your desired start and end date:

```
<> sudo isight_connector -s MM-DD-YYYY -e MM-DD-YYYY
```



Threat Intelligence Services Custom Feeds Historic Pull Commands

Custom feeds provided by Threat Intelligence Services provide a mechanism for you to generate a historic pull during the initial feed run. After the initial feed run, feeds typically perform an hourly pull, but can be adjusted within cron.

Refer to the documentation for your custom feed or integration for more information.

Reset User Password



You cannot reset a SAML nor LDAP user's password from the command line.

If you have root access to your ThreatQ installation, you can reset any user's password from the command line.

- 1. SSH to your ThreatQ installation as root.
- 2. Navigate to the api directory:
 - <> cd /var/www/api
- 3. Run the following command:
 - <> php artisan threatq:password-reset
- 4. At the prompt, enter the email address for the user whose password you are resetting.
- 5. At the prompt, enter the new password.
- 6. At the prompt, re-enter the new password to confirm.

Update TLP Designations

Use the following command to update the TLP schema for an Object Source or Object Attribute Source with the source's default TLP designation.



See Traffic Light Protocol (TLP) topic for more details on setting a default TLP designation for a source.



You should use this command to update your system to match default TLP configurations, specifically attributes and sources that were added to the Threat Library prior to the release of the TLP feature introduced with ThreatQ 4.11. This command will override previous TLP schema settings for a source including ones set by users. You will be prompted to confirm the action after entering the command. All updates will be recorded in the audit log.



The command will update using the default TLP designation. If a default designation is set to None, all references to the source will be updated to None.

Update All Sources

- 1. SSH to your ThreatQ installation.
- 2. Navigate to the api directory using the following command:

```
<> cd /var/www/api
```

3. Run the following command:

```
<> sudo php artisan threatq:apply-tlp-defaults
```

- 4. The application will warn you that this action is not reversible and will require user confirmation before proceeding.
- 5. Type **Yes** to confirm and proceed with the action.



The application will automatically be placed into maintenance mode. After the command has completed its operation, the application will be automatically be brought out of maintenance mode.

Update a Specific Source

- 1. SSH to your ThreatQ installation.
- 2. Navigate to the api directory using the following command:

```
<> cd /var/www/api
```

3. Run the following command:



<> sudo php artisan threatq:apply-tlp-defaults --sources="<your source>"



You can apply the command to multiple sources by listing the sources in a comma-delimited format.

Example: --sources="CrowdStrike, AlienVault"

- 4. The application will warn you that this action is not reversible and will require user confirmation before proceeding.
- 5. Type **Yes** to confirm and proceed with the action.



The application will automatically be placed into maintenance mode. After the command has completed its operation, the application will be automatically be brought out of maintenance mode.

Convert TLP

Use the following command to update all object sources and object attribute sources that have TLP stored as an object attribute. This command will not affect TLP attributes that have already been converted. Users should use this command for new incoming data, such as migrating data into the system, which has TLP attributes but no TLP set.

- 1. SSH to your ThreatQ installation.
- 2. Navigate to the api directory using the following command:

```
<> cd /var/www/api
```

- 3. Place the application into maintenance mode see the Maintenance Mode section.
- 4. Run the following command:

```
<> sudo php artisan threatq:convert-tlp-attributes
```

5. Bring the application out of maintenance mode - see the Maintenance Mode section.

Use Scenarios:



Object has one or more TLP Attributes with an invalid TLP (not currently in the TLP options)

- If the Object has just one TLP Attribute none of its Sources or Attribute Sources will be updated.
- If the Object has more than one TLP Attribute any Sources or Attribute Sources that match the Attribute Source of the TLP Attribute will not be updated.

Object has a single valid TLP Attribute

 All of the Object Sources and Object Attribute Sources will be updated to match the value of the TLP Attribute.

Object has multiple TLP Attributes

- Each TLP Attribute will be evaluated separately.
- Any Object Sources or Object Attribute Sources whose source matches that of the TLP Attribute will be updated with the value of the TLP Attribute.
- Any Object Sources or Object Attribute Sources whose sources do not match will not be updated.
- If there are no matches at all between the source of the TLP Attribute and any of the Object Sources or Object Attribute Sources, a new Object Source will be added using the Attribute's TLP value. Each of the Object Attributes will receive a new Object Attribute Source with the TLP value as well.

View Feed Queues

When upgrading a feed, it is recommended to allow the previous implementation the feed to complete processing of the data it has already downloaded, prior to upgrade, to avoid any data loss.

Perform the following steps to confirm that the queues have been cleared.

1. Run the following command:

```
<> /var/www/api/artisan threatq:list-queues -p feeds
```

2. Locate and confirm that the feed's Indicators and Reports rows display a value of "0" for the Messages Ready and Messages Unacknowledged columns.



The queues should be cleared, reporting 0 values, before proceeding with the update.



Airgap Import

See the threatq:sync-import topic.

Airgap Export

See the threatq:sync-export topic.



Dashboards

Upon install, the system default ThreatQ dashboard serves as your initial landing page when you log into ThreatQ.


While this dashboard cannot be modified, you can create your own data-driven dashboards.

Users with roles of Primary Contributor, Administrators, and Maintenance can create custom dashboards that can be shared with individual users or all users.



Default Dashboard

The system default dashboard, Overview, displays metrics and visualizations to provide at-a-glance views of your threat intelligence data.



Widgets include:

- Overview of intelligence by score
- Watchlist activity
- · Incoming intelligence
- Open assigned tasks

Overview by Intelligence Score

This dashboard graph provides a summary of indicator scoring in the system. It lists total indicators by score in the following order:

- Very High
- High
- Medium
- Low




- · Very Low
- Not Scored

You may click on the percentage/number of indicators to launch an advanced search based on that criteria.



Incoming Intelligence

This dashboard graph provides a view of threat intelligence from all incoming feeds.






The system categorizes threat intelligence by:

- Feed Name
- Total number of indicators reported by a source
- Indicators reported by a source with a status of active
- All indicators reported by a source per day (includes existing indicators)

Clicking on the **Total** and Active values will navigate you to the Threat Library Advanced Search page with the appropriate filters applied

Watchlist Activity

This dashboard section provides a view of the intelligence data that you selected to watch. You may click on any accompanying link to view the details page of the item being watched.



See the Add/Remove an Object to the Watchlist topic for steps on how to add an object to your watchlist.



Tasks


This dashboard widget provides a view of all open tasks in the platform. You can view your open tasks or view all open tasks. Tasks on the dashboard are categorized by:

- Task ID
- Task Name
- User the Task is Assigned To
- Due Date
- Status



Custom Dashboards

You can create and share multiple custom dashboards to be used on the ThreatQ landing



Each dashboard is comprised of system widgets which are populated by data derived from data collections - see Managing Search Results topic for more details. You can click on an individual segment of data within a widget to view it in the ThreatQ Threat Library.

With the dashboard sharing option, you can determine which dashboards you want to share with other users and which ones you want to keep private. See the Dashboard Sharing topic for more details.

You can control which shared dashboards created by other users appear in your view. Dashboards added to your view will appear dashboard horizontal menu as well as the Dashboards dropdown menu. You can also remove your own dashboards from your view without deleting them from the platform. See the User View Management topic for more details.

Topics covered in this section include:

SECTION	DETAILS
Analytics Dashboards	Deploy pre-configured dashboards for Adversaries, Events, Files, and Indicators.



Dashboard Widgets	You can add the following widgets to your custom dashboards: Bar Chart, Description, Line Chart, Pie Chart, Count, and Table.
Dashboard Management	You can create, edit, and delete your own custom dashboards.
Dashboard Sharing	You have the ability to configure how your custom dashboards are shared across the ThreatQ platform.
User View Management	Add, remove, and reorder dashboards that you created or have been shared with you.



Analytics Dashboards

You can deploy preconfigured dashboards, formerly known as Analytics, to your dashboard view.



Analytics dashboards cannot be edited.

Options include:

SECTION	DETAILS
Adversaries Analytics	The Adversaries dashboard provides an overview of all the adversaries within ThreatQ as well as overlapping use of specific indicators.
Events Analytics	The Events dashboard provides a high-level view of what types of events have occurred and how frequently they are occurring.
Files Analytics	The Files dashboard provides you with a pie chart displays the percentage of different types of files within the system and a table that lists the files, the date and time they were created, their title, their source, their category, and associated keywords.
Indicators Analytics	The Indicators Dashboard provides an insight into what indicators have been added to the system within the last 15 days, as well as an overview of how many indicators fall under each indicator type.




Adversaries Analytics Dashboard

The Adversaries dashboard provides an overview of all the adversaries within ThreatQ as well as overlapping use of specific indicators.

Adversaries Summary Table

The Adversaries Summary table lists adversaries by name, number of indicators, date created, and the most recent event date associated with the adversary.



FUNCTION	DETAILS
Opening the Adversary Details page for an adversary	Click the name in the Adversary Name column.
Performing a search for related indicators	Click the number in the Number of Indicators column to set the adversary name as a search criterion and open the Advanced Search page.



FUNCTION	DETAILS
Opening the Event Details page for an adversary event	Click the date in the Most Recent Event Date to open the Event Details page.
Changing the number of entries displayed in the table	Click the paging batch option located to the bottom-right of the table.
Sorting the table by a column	Click the column header. To reverse the column sorting order, click the header a second time.
Searching within the Adversary Name column	Click within the search box at the top of the column, and enter your search criteria.

Adversaries Overlap Table

The Adversary Overlap table lists adversaries, the date and time they were created, their type, and any overlapping indicators.




FUNCTION	DETAILS
Opening the Adversary Details page for an adversary	Click the name in the Adversary Name column.
Opening the Indicator Details page for an overlapping indicator	Click the identity in the Overlapping Indicator column.



FUNCTION	DETAILS
Changing the number of entries displayed in the table	Click the paging batch option located to the bottom-right of the table.
Sorting the table by a column	Click the column header. To reverse the column sorting order, click the header a second time.
Searching within a column	Click within the search box at the top of the column, and enter your search criteria.

Indicator Distribution Pie Chart

The Adversary Overlap table lists adversaries, the date and time they were created, their type, and any overlapping indicators.



FUNCTION	DETAILS
Viewing more information about a selected value	Hover over a colored section of the pie chart to open a popup identifying the indicator.



FUNCTION	DETAILS
	The number of times the indicator was found within the specified time frame, and what percentage of the total number of indicators it represents.
Hiding or unhiding one of the values from the pie chart	Click the indicator on the left of the pie chart to remove it; click a second time to reinstate it.
Adjusting the time frame of the information displayed	Click the dropdown menu at the top right and select the desired timeframe. You can select from: Last 24 Hours Last 7 Days Last 30 Days Last Year User-set custom range
Printing the graph or saving it as a PNG, JPEG, PDF, or SVG	Click the hamburger menu ≡ and select the desired option.



Events Analytics Dashboard

The Events dashboard provides a high-level view of what types of events have occurred and how frequently they are occurring.










Events History Scatter Plot

The scatter plot points are plotted by date (x-axis) and hour (y-axis). The legend under the scatter plot identifies the different kinds of events shown.



The following functions are available:

FUNCTION DETAILS

Viewing an event's name, date and time, and source

Hover your mouse over an event on the scatter plot to see its name, date and time, and source.



Opening the Event Details page for one of the events

Click the event in the scatter plot.

For more information, see Object Details.




FUNCTION	DETAILS
Hiding or unhiding one or more of the event types	Click the event type in the legend immediately below the scatter plot to remove it from the graph; click it again to reinstate it.
Adjusting the time frame of the information displayed	Click the dropdown menu at the top right and select the desired time frame. You can select from: Last 24 Hours Last 7 Days Last 30 Days Last Year User-set custom range
Printing or downloading the scatter plot as a PNG, JPEG, PDF, or SVG file	 Click the hamburger menu ■ and select the desired option.

Monthly Heatmap

The Monthly Heatmap table lists events that happened per adversary each month. Shading of the monthly totals is used to allow you to quickly scan for patterns in the events and to quickly



detect events with higher monthly counts.




The following functions are available:

FUNCTION

DETAILS

Viewing an event's name and monthly count

1. Hover your mouse over an event on the heatmap to see its name and monthly count.



Adjusting the time frame of the information displayed

1. Click the dropdown menu at the top right and select the desired time frame.

You can select from:

- Last 24 Hours
- Last 7 Days




- Last 30 Days
- Last Year
- User-set custom range

Printing the graph or saving it as a PNG, JPEG, PDF, or SVG

1. Click the hamburger menu ≡ and select the desired option.

New Events Summary

The New Events Summary table provides a breakdown of events by date, type, title, and



sources.

The following functions are available:

FUNCTION DETAILS

Opening the Event Details page for one of the events

Click the event title.

For more information, see Object Details.




FUNCTION	DETAILS
Changing the number of entries displayed in the table	Click the dropdown menu at the top right of the table, and select the desired option.
Sorting the table by a column	Click the column header. Click on the header a second time to reverse the sort order.
Searching within a column	Click within the search box at the top of the column, and enter your search criteria.



Files Analytics Dashboard

The Files dashboard provides you with a pie chart displays the percentage of different types of files within the system and a table that lists the files, the date and time they were created, their title, their source, their category, and associated keywords.








Files Pie Chart

The File Types pie chart displays the percentage of different types of files within the system.




The following function is available:

FUNCTION

DETAILS

Viewing more information about a selected file

Hover over a colored section of the pie chart to open a popup that gives the number of attachment types.




Printing the graph or saving it as a PNG, JPEG, PDF, or SVG

Click the hamburger menu \equiv and select the desired option.



Files Table

Immediately below the Browse pie chart is a table that lists the files, the date and time they were created, their title, their source, their category, and associated keywords.



FUNCTION	DETAILS
Opening the File Details page for a file	Click the name in the Title column.
Changing the number of entries displayed in the table per page	Click the paging batch option located to the bottom-right of the table.
Sorting the table by a column	Click the column header. Click on the header a second time to reverse the column sorting order.
Searching within a column	Click within the search box at the top of a column, and enter your search criteria.



Downloading a file

Click the download $\stackrel{\checkmark}{\underline{}}$ icon.



Indicators Analytics Dashboard

The Indicators Dashboard provides an insight into what indicators have been added to the system within the last 15 days, as well as an overview of how many indicators fall under each indicator type.

Recently Created Indicators Histogram

The histogram is organized by date. Daily indicator totals are at the top of each column. Each bar is broken down into colors, one for each indicator type.



The following functions are available:

FUNCTION DETAILS

Viewing the number of indicators created each day by type

Hover over a colored section to view a popup showing how many attempts of a particular type (for example, MD5, SHA-1, SHA-256) were made on that date.





Zooming in for a closer view

1. Drag your mouse over a section of the histogram, and your view will be magnified.




2. Click **Reset Zoom** to return to the full histogram.

Printing the histogram or downloading it as a PNG, JPEG, PDF, or SVG file Click the hamburger menu \equiv , and select the desired option.



Most Recent 100 Indicators

The Most Recent 100 Indicators list displays the 100 most recently reported indicators.




FUNCTION	DETAILS
Resort the Table	Click on the different table headings to resort that table by that column.
Search and Filter Table Results	Click on one of the search boxes at the top of the columns and enter a keyword to filter the results. You can use the supplied dropdown selections for the Status and Type columns to filter by system-available values.
Modify the Number of Rows Displayed	Click on the Row Count icon located to the top-right of the chart and select a new display count from the dropdown.



Access the Indicator Details Page for a Specific Indicator Click on the specific Indicator to review to open the Indicator's Details page.

Attributes Table

The attributes list on the left side displays attributes related to indicators in your system.




FUNCTION	DETAILS
Change the Number of Entries Displayed in the Table	Click the Row Count icon located to the top-right of the chart and select a new display count from the dropdown.
Search/Filter Attributes and Values	Click within the search box at the top of the column, and enter your search criteria.



View More Information About a Selected Attribute

1. Click on an attribute row in the table to view additional information in the right pane.




- 2. Hover the mouse over different portions of the pie chart to reveal the segment's value.
- 3. Click on an **Attribute Value** in the summary table below the pie chart to open the Advanced Search page with those attribute values applied.



Recent Sources

The Recent Sources Scatter plot displays how many indicators were provided by a given source each day within a specified time frame.




The following functions are available:

FUNCTION

DETAILS

View the Date and Number of Indicators from a Given Source

1. Hover the mouse over one of the scatter plot circles to view a popup with the Source, Date, Time and Number of Indicators.



2. Click on the one of the scatter plot circles to open the Advanced Search page with the specific filter settings used for that selection.



Adjust the Date Range of the Information Displayed

The default date range is 30 days.

1. Click the date range icon located to the top-right of the chart and use the dropdown menu select the desired range.

You can select from:

- Last 24 Hours
- Last 7 Days
- Last 30 Days
- Last Year
- User-set custom range

Hide Values from the Scatterplot

1. Click on a source in the legend under the scatter plot to hide it.

The Source will be removed from the scatter plot and the source in the legend appear grayed out.


2. Click on the source again to add it back to the scatter plot.

Attack Phases

Attack Phases are the ways an indicator might be used and are listed as indicator attributes. The Attack Phases pie chart displays the number of indicators that fall under each attack



phase.



The following functions are available:

FUNCTION DETAILS

View the Number of Indicators for an Attack Phase

- 1. Hover the mouse over a portion of the pie chart to view a popup the Attack Phase and number of indicators associated with it.
- 2. Clicking on a pie chart section will open the Advanced Search page with the specific filter settings used for that selection.

Adjust the Date Range for the Information Displayed

The default Date Range is 30 days.

1. Click the date range icon located to the top-right of the chart and use the dropdown menu select the desired range.

Users can select from:

- Last 24 Hours
- Last 7 Days
- Last 30 Days
- Last Year



User-set custom range

Hide a Values from the Pie Chart

1. Click on a Attack Phase in the legend to the left of the pie chart to hide it.

The Attack Phase will be removed from the pie chart and the source in the legend appear greyed out.

2. Click on the Attack Phase again to add it back to the pie chart.



Dashboard Widgets


You can use the following widgets to build your custom dashboards: Bar Chart, Description, Line Chart, Pie Chart, Count, and Table.

Bar Chart



You can click on individual bars within the chart to view those results in the Threat Library.

Complete the following fields to add a Bar Chart widget to your custom dashboard.



FIELD DESCRIPTION

Title The title that will appear above the widget.

Automatically The refresh time for the data. Options include:
Update

• 15 Minutes

• 30 Minutes

• 60 Minutes




FIELD	DESCRIPTION
	• None
Data Collection	Select the data collection to populate the data.
Object	Select a specific object type to display.
Group By	Select a data column to sort the information such as source, tags, etc.
Visual Display	Select whether to show the bar chart horizontally or vertically.
Show Top Options	Select the number of results to display. Options include:Top 5Top 10



Description

The Description widget allows you to provide further context and additional instructions for your custom dashboard. You can use the supplied editor to format your content.



Line Chart

The Line Chart widget displays object information in a linear graph using the following date stamps:

- Date Created (all object types)
- Last Modified (all object types
- Expiration Date (indicators only)





Complete the following fields to add a line chart widget to your custom dashboard.



Time Segments


FIELD	DESCRIPTION
Title	The title that will appear above the widget.
Automatically Update	The refresh time for the data. Options include: • 15 Minutes • 30 Minutes • 60 Minutes • None
Data to Show in Widget	Select the data collection to populate the data.
Object	Select a specific object type to display.
Date Metric	 The date stamp to use with the line chart. Options include: Date Created (all object types) Last Modified (all object types) Expiration Date (indicators only)
Time Range	The time range from today to be displayed. Options include: • 1 Week • 3 Months • 6 Months • 1 Year

Select how the dates will be displayed on the line chart. Options



Count

The Count widget displays the total number a specific object type. You can configure the widget to display a different background color if the total number of objects associated with the widget is above or below a specific value.



Complete the following fields to add a Count widget to your custom dashboard.

FIELD	DESCRIPTION
Title	The title that will appear above the widget.
Automatically Update	The refresh time for the data. Options include:15 Minutes30 Minutes60 MinutesNone

Select the data collection to populate the data.

Data to Show in

Widget




FIELD	DESCRIPTION
Object	Select a specific object type to display.
Emphasize Data Using Color	Check this box to use different colors to highlight the widget if the count is less than or greater than a specific value. If checked, you will be prompted to select a count value and background color.

Pie Chart



You can click on individual segments within the chart to view those results in the Threat Library.

Complete the following fields to add a Pie Chart widget to your custom dashboard.



FIELD DESCRIPTION

Title The title that will appear above the widget.



FIELD	DESCRIPTION
Automatically Update	The refresh time for the data. Options include: • 15 Minutes • 30 Minutes • 60 Minutes • None
Data Collection	Select the data collection to populate the data.
Object	Select a specific object type to display.
Group By	Select a data column to sort the information such as source, tags, etc.

Table

Table widgets allow you to add as many column fields as needed. You can click on a row's **value** entry to view it in the ThreatQ Threat Library. You can also click on the **eye** icon for a



row to view a preview of the system object.



Complete the following fields to add a Table widget to your custom dashboard.

FIELD	DESCRIPTION
Title	The title that will appear above the widget.
Automatically Update	The refresh time for the data. Options include: • 15 Minutes • 30 Minutes • 60 Minutes • None
Data Collection	Select the data collection to populate the data.
Object	Select a specific object type to display.



FIELD	DESCRIPTION
Group By	Select a data column to sort the information such as source, tags, etc.
Manage Columns	Select the data columns to display in the table.
Sorting	Select the column to sort the table and the order (ascending/descending).



Dashboard Management

Access to dashboards is determined by your user role and Sharing permission level.


Accessing a Dashboard

If your dashboard view includes more tabs than can be displayed in a single screen, the left and right arrows on the right side of the screen allow you to scroll through the list of dashboard tabs.




You can access a specific custom dashboard using the following methods:

• Click the **Dashboards** link in the top navigation and select a dashboard from the dropdown menu.



When viewing a dashboard, click another dashboard tab. If you are not viewing a
dashboard at the time, you can click on the ThreatQ logo to load your default
dashboard.





After you select a dashboard, you can click the licon next to the dashboard name to view:

- Dashboard owner
- Date and time of the last change to the dashboard




Add an Existing Dashboard to Your View

You can customize your dashboard view by adding a dashboard you created, a default dashboard, or a dashboard shared with you by another user.

- 1. Navigate to the ThreatQ landing page.
- 2. Click the Add Dashboard link.
 The Add Dashboard window lists any dashboards available to you (default, shared, or



owned).




3. Click the dashboard you want to add to your view.

Creating a Dashboard


All User Roles, except Read-Only Access can create custom dashboards.

- 1. Navigate to the ThreatQ landing page.
- 2. Click one of the following options:
 - Create New Dashboard If your view includes all the dashboards that you created and that are shared with you, click this link to begin creating a new dashboard.
 - Add Dashboard If your view does not include all of the dashboards you created or that are shared with you, click this link to access the Add Dashboard window and then click the Create New Dashboard button.






3. Enter the **Dashboard Name**.




4. Click the Add Widget button and select the type of widget to add.



- 5. After adding a widget, you can resize it by clicking and dragging the mouse on the bottom-right grey corner.
- 6. You can move the widget around the dashboard by clicking the widget header and dragging it around the page.



7. Click on the **Share** button and specify user access to the dashboard. See the Dashboard Sharing topic for more details.



8. Click the **Done Editing** button to save the dashboard.

Editing a Dashboard

You can only edit a Dashboard for which you have owner or editor permissions.

- 1. Switch to the custom dashboard you want to edit.
- 2. Click the Edit button.





3. You can click the gear icon in the header of a widget to edit individual widget settings. You can click the delete icon to delete the widget.



If you add and save a new widget that references a data collection, all users who have access to the dashboard are also granted viewing access to the data collection.


4. After you make your changes, click the **Done Editing** button to save all updates.

Deleting a Dashboard

This action will delete the dashboard from the platform. You can also remove a dashboard from your view without completely deleting it from the platform. See the User View Management topic for more details.

You cannot delete the default system dashboard or dashboards created by other users.

- 1. Switch to the custom dashboard you want to delete.
- 2. Click the Edit Dashboard button.
- 3. Click the red delete icon next to the **Done Editing** button.



4. Confirm the deletion by clicking the **Delete Dashboard** button in the **Are you sure?** window.




Reassigning a Dashboard of a Deleted User

When you delete a user, you must reassign ownership of his dashboards or they will be automatically deleted with his account. See the Managing User Accounts topic for more details.



Dashboard Sharing

Owners and editors have the option to share a dashboard with other users. However, only the dashboard owner can remove a user's permissions entirely. In addition, the Share(d) button displayed to depends on your permission level and the sharing status of the dashboard.



See the Sharing topic for more information on the user and group-level permissions you can assign to each dashboard.

Sharing a Dashboard


Dashboard owners and editors can update sharing settings for a dashboard at any time.

1. Enter a dashboard's **Edit** view.



2. Click the **Share** button.

The Sharing window allows you to select the user(s) to which you want to grant access.




- 3. Click the arrow next to the <a> icon to select the user's permission level.
 - If you are granting access to all users, you must select the **Can View** option. You can only assign editing permission to individual users not to all users.
 - If you assign owner permissions to another user, your permissions automatically change to editor-level.
- 4. Use the search field to locate and select a user's name or the **Everybody (Public)** option. This option grants view-only access to all users.
 - The user is now listed in the **Who has access** list. From this listing, you can change or delete the user's permissions.
 - When you share a dashboard with a user, you also give him viewing permissions for all data collections used by the dashboard's widgets.
- 5. Click the Apply button to save the user's permission level.



Updating Dashboard Permissions

- 1. Enter a dashboard's Edit view.
- 2. Click the **Share** button. The Sharing window lists the users who have access to the dashboard.



- 3. From the Sharing window, you can:
 - **Remove a user's permissions** If you are the dashboard owner, click the trashcan icon to the right of the user name.
 - Change a user's permission Click the arrow next to the user's current permission icon and select a new permission level.
- 4. Click the **Apply** button to save the user's permission level.

Shared Dashboards of a Deleted User

When you delete the owner of a dashboard from the platform, ThreatQ prompts you to reassign the dashboard to another user or to delete it. See the Managing User Accounts topic for more details.



Dashboard Export


When you select a custom dashboard, the PDF Preview button gives you the option to export a PDF copy of all the widgets in the dashboard. The PDF preview window allows you to rearrange the widget order before you print and/or save the PDF.



You cannot export the default dashboard or the Analytics dashboards to PDF.

Creating a Dashboard PDF

- 1. Navigate to the ThreatQ landing page.
- 2. Click a custom dashboard.
- 3. Click the **PDF Preview** button.



4. Review the layout of the PDF. You can use the following methods to customize the widget display:





ThreatQ saves your changes locally so that you do not have to repeat the process the next time you generate a PDF for the dashboard.

- Click a widget header then drag and drop to move it to a new location on the page.
- Resize a widget by clicking and dragging the bottom-right grey corner.
- 5. Click the **Export to PDF** button.

The system exports the dashboard widgets to a PDF file which you can save and/or print. The PDF file name defaults to dashboard.pdf. The PDF title includes the ThreatQ logo and the name of your dashboard.



Do not attempt to resized your browser window during PDF generation.

Sample PDF:

THREAT() Head Office





User View Management

The User View refers to your individual view of the ThreatQ landing page. You can create custom dashboards and manage which dashboards, both shared and your own custom ones, appear in your view.




Any dashboard that is part of your User View will also be listed in the Dashboards dropdown menu.

Adding a Dashboard to Your View

You can add dashboards that have been shared with you as well as your own private dashboards that are not currently part of your view.

- 1. Navigate to the ThreatQ landing page.
- 2. Click the Add Dashboard button.






If there are no available shared dashboards, the **Add Dashboard** link will be replaced with **Create New Dashboard**.



The Add Dashboard window lists the dashboards that have been shared with you and any of your private dashboards that are not currently part of your view.




3. Click a dashboard in the list to add it to your view.

Removing a Dashboard from Your View

You can remove a shared dashboard created by another user from your view as well as your own dashboards. This process does not delete the dashboard from the platform. See the Dashboard Management topic for instructions on how to delete a dashboard.

1. Hover your cursor over the name of the dashboard you want to remove.

An X icon will appear to the right of the dashboard name.



2. Click the **X** to remove the dashboard from your view.

Changing Dashboard Order

You can change the order of dashboard tabs listed in your view, including the default Overview tab.

- 1. Navigate to a custom dashboard.
- 2. Click and hold the mouse down over a dashboard tab.
- 3. Drag the tab to your desired order and release the mouse button.





Order changes are saved automatically. These changes also update the order in the Dashboards dropdown menu.



Data Controls

The Data Controls section of the ThreatQ platform allows you to setup and configure:

SECTION	DETAILS
Indicator Expiration	Configure expiration policies to automatically deprecate stale intelligence as it becomes less relevant.
Scoring Algorithms	Configure scoring to filter through the millions of indicators your platform has ingested to focus on the data that really applies to your environment while retaining all other indicators and context for threat research.
Traffic Light Protocol (TLP)	Configure your Traffic Light Protocol (TLP) schema to provide a set of designations to ensure that sensitive information is shared with the appropriate audience.
Whitelisted Indicators	Identify non-malicious indicators using the Whitelist feature.



Indicator Expiration

Automatic expiration allows you to deprecate stale intelligence based on a set of defined criteria. As the data becomes less relevant, ThreatQ sets the status to Expired, which relieves the data burden on your team or infrastructure.

Accessing the Indicator Expiration Page

1. From the navigation menu, click on Threat Library and select **Indicator Expiration** under the *Data Controls* heading.

The Data Controls page will open with the Indicator Expiration tab selected by default. THREATQ 🍑 ⚠ Threat Library **Data Controls** Indicator Expiration Inburden your team from the task of manually deprecating intelligence. Based on a set of criteria defined and controlled by you, threat intelligence will automatically expire as it becomes less relevant Q. Search for a source. Domain Tools Don't automatically expire Exceptions > Emerging Threats Don't automatically expire Exceptions > MITRE Enterprise ATT&CK Exceptions > Exceptions > threatg@threatg.com Don't automatically expire Exceptions >

How ThreatQ Calculates Expiration Dates

SCENARIO

DESCRIPTION

Indicator Reported by
Source with an new source that has an expiration policy, ThreatQ will set the Expiration Policy



	expiration date using the policy with the greater expiration date.
Indicator Report by a Source with an Expiration Policy of Never Expire	If an indicator has an expiration date and it's reported by a new source that has an expiration policy of Never Expire, ThreatQ sets that indicator to Never Expire.
Indicator Reported by a Source with an Exception for that Indicator	If an indicator is reported by a source that has an exception for the indicator, the exception expiration date will be used regardless of the greater expiration date. An exception takes precedence over the source's expire policy.
Indicator Reported by Two Different Sources	If an indicator is reported by a source with an Expiration Policy and then reported by a second source with another Expiration Policy, the greatest expiration date is selected to set the expiration date. The expiration date will be set based on the date the second source reported the indicator.
Indicator Reported by Two Different Sources, one with an Exception	If an indicator is reported by a source that has an exception for the indicator and then reported by a second source, the greatest expiration date is selected despite the exception. The expiration date will be set based on the date the second source reported the indicator.

Selecting an Expiration Policy per Feed

You can choose from three options when configuring an expiration policy for a source of intelligence:



OPTION DESCRIPTION


Don't automatically expire (No policy set)

ThreatQ sets all feeds to **Don't Automatically Expire** until an analyst decides otherwise. When set, indicators reported from this specific feed do not have an expiration date automatically applied to them.

If an indicator is reported by Source A (an intelligence feed without an expiration policy), and is later reported by Source B (an intelligence feed that expires data in 7 days), ThreatQ sets the indicators to automatically expire in 7 days.

Automatically Expire Indicators

When setting a specific intelligence feed to **Automatically Expire Indicators**, ThreatQ requires you to provide a specific number of days. After you configure this setting, it applies to all intelligence currently in the system, as well as new intelligence as it is ingested. ThreatQ calculates the appropriate expiration date based on the number of days from ingestion. Once an indicator's expiration date is met, its status changes to **Expired**.



Never Expire

Using this setting ensures that all intelligence reported by a specific feed is protected from automatic expiration, regardless of scenario.




Adding Exceptions

ThreatQ allows you to add exceptions based on specific indicator types within in a feed in addition to setting an expiration policy at a global level for all intelligence ingested by a specific feed.

1. From the navigation menu, click on Threat Library and select **Indicator Expiration** under the *Data Controls* heading.


The Data Controls page will open with the Indicator Expiration tab selected by default.




- 2. Locate the source.
- 3. Click **Exceptions** to expand the option.



The Exceptions option menu opens.





- 4. Click Add Exception.
- 5. Select the **Indicator Type** from the dropdown.
- 6. Enter the number of days after the item has been ingested before expiring.

Repeat steps 4-6 to add multiple

- 7. Click on **Delete** next to the row to delete an exception.
- 8. Click on Save.

Applying Expiration Policy Changes to Data

When updating an expiration policy, the system now applies the update to all selected existing data in the platform to honor the new policy. This process can take a while based on system resources and the number of indicators in the system.



Refer to the following table for estimates on the total time required for the system to apply the selected policy to existing data, based on the following criteria:

• Dataset: 6 Million Indicators

• System Specifications: 32GB VM 4 vCPU

INDICATORS TO RESET EXPIRATION OUT OF 6M TOTAL INDICATORS	RESET AND RECALCULATE EXPIRATION	EXPIRE INDICATORS	TOTAL TIME FOR RESET
50,000	3 hours and 30 minutes	53 seconds	3 hours 31 minutes
100,000	4 hours and 51 minutes	1.8 minutes	4 hours 53 minutes
200,000	10 hours 20 minutes	3.5 minutes	10 hours 24 minutes
1.2 million	2 days 7 hours 4 minutes	35 minutes	2 days 7 hours 40 minutes
3.1 million	3 days 16 hours 42 minutes	3.5 hours	3 days 20 hours
5.3 million	4 days 7 hours 17 minutes	4.7 hours	4 days 12 hours



Common Expiration Policy Scenarios

SCENARIO

DESCRIPTION

An indicator is reported by a single source (with an expiration policy)

- 1. On 10/1, Source A reports the indicator and the expiration date is set to 10/8.
- 2. When the date switches from 10/7 to 10/8, this indicator is queued to have its status changed to **Expired**.

An indicator is reported by Source A (with an expiration policy of 7 days) and 3 days later is reported by Source B (with an expiration policy of 10 days).

- 1. On 10/1, Source A reports the indicator and the expiration date is set to 10/8.
- 2. Source B reports the same indicator 3 days later (10/4). The indicator's expiration date is set using the greatest expiration date between the two sources. In this example, the new expiration date will be 10/14 (10 days from when it was reported by Source B).
- 3. When the date switches from 10/14 to 10/15, this indicator is queued to have its status changed to **Expired**.

An indicator is reported by Source A (with an expiration policy of 7 days) and is later reported by Source B (with an expiration policy of Never Expire).

- 1. On 10/1, Source A reports the indicator and the expiration date is set to 7 days.
- 2. Source B reports the same indicator 3 days later with a policy of **Never Expire**. The indicator's expiration date is removed and the indicator is now set to **Protect from auto-expiration**.

An indicator is currently set to Expired and is reported by Source A (with an expiration policy of 7 days).

- 1. On 10/1, an indicator is in ThreatQ with a status of **Expired**.
- 2. On 10/1, Source A reports the indicator. The status of the indicator changes to whatever the



SCENARIO	DESCRIPTION
	default status is for Source A and the expiration date is set to 10/8.
	When the date switches from 10/7 to 10/8, this indicator is queued to have its status changed to Expired.
An indicator is currently set to	 An indicator is in ThreatQ with a status of Expired.
Expired and is reported by Source A (with an expiration policy of Never Expire).	Source A, with an expiration policy of Never Expire, reports the indicator. The expiration of that indicator changes to Protect from auto-

expiration.

A FQDN indicator is reported by Source A (with an expiration policy of 10 days with an exception for 5 days for FQDN indicators) and is later reported by Source B (with an expiration policy of 15 days).

- 1. On 10/1, Source A reports the FQDN indicator and the expiration date is set to 10/6.
 - An exception takes precedence over the source's expire policy.
- 2. Source B reports the same indicator 1 day later (10/2). The indicator's expiration date is set using the greatest expiration date between the two sources. In this example, the new expiration date will be 10/17 (15 days from when it was reported by Source B).
- 3. When the date switches from 10/17 to 10/18, this indicator is queued to have its status changed to **Expired**.




Scoring Algorithms

As indicators are added to the system, ThreatQ's scoring algorithm automatically calculates and assigns a score based on the weighting you established.

By configuring scoring, you can filter through the millions of indicators it may have collected to focus on the 10% that really apply to your environment while still retaining all other indicators and context for threat research.

Accessing the Scoring Sensitivity Page

1. From the navigation menu, click on Threat Library and select **Scoring** under the *Data Controls* heading.



Scoring Criteria

As you build a scoring algorithm, you influence indicator scores based on the following criteria:


Indicator Type



- Indicator Source
- Attributes
- · Adversary Relationship

Configuring Your Scoring Algorithm

- 1. Select the criteria tab to influence your scoring.
- 2. Use the slider to determine the sensitivity of the criterion you select.



- 3. Use the sliders to increase or decrease the weighting for the criteria.
 - You may increase the score up to 10, which creates a score of **Very High**. You may also decrease the score, which creates a score of **Very Low**.
- 4. Click on **Apply** to save changes.



Traffic Light Protocol (TLP)

Traffic Light Protocol (TLP) schema provides a set of designations used to ensure that sensitive information is shared with the appropriate audience. ThreatQ provides a method for designating the availability of intelligence information by their sources. Users can also use TLP schema to filter objects when creating an export - see the **Adding an Export** section in the Managing Exports topic for more details.



Administrators have the ability to configure TLP visibility settings for the ThreatQ application.

Designations

TLP employs four lights to indicate the expected sharing boundaries for data:

LIGHT	DESIGNATION	DESCRIPTION
•	Red	Not for disclosure, restricted to participants only.
	Amber	Limited disclosure, restricted to participant's organizations.
•	Green	Limited disclosure, restricted to the community.
\bigcirc	White	Disclosure is not limited.

TLP Assignment Hierarchy

The ThreatQ TLP assignment hierarchy is as follows (highest to lowest precedence):

METHOD	DETAILS
Manually Set	Using the Add New Source option when creating an object will allow you to select a TLP designation.




Source Provided Data	TLP information received from ingested data.
Source Default	Administrators can set a source's default TLP designation. See the Add TLP to Source section.
No TLP	A TLP designation has not been set for the source.

Access TLP Settings

Users can manage TLP settings for system sources by accessing the **TLP** tab under the **Data Controls** page.

1. From the navigation menu, click on Threat Library and select **TLP** under the *Data Controls* heading.

The Data Controls page will load with TLP tab selected by default.



Configure TLP Visibility

System administrators can set visibility settings to either hide or show TLP designation lights to users.



Enabled indicates that TLP designations are visible to users.

1. Click on the **Enable/Disable** toggle switch located to the top-right of the TLP page.






Administrators will not need to click on the **Save** button, changes will be made upon clicking on the switch.

Apply a TLP Designation to Source

1. Locate the source to update from the list provided.






2. Click on the TLP dropdown to the right of the source and select the appropriate TLP designation.

TLP (Traffic Light Protocol)

TLP is a set of designations used to ensure that sensitive information is shared with the approprial sources. TLP employs four colors to indicate expected sharing boundaries for data. How it works



3. Click on Save.



You can override a source-default TLP designation when manually adding a source to an object. See the Adding a Source to an Object topic for more details.



Whitelisted Indicators


There are some indicators that should be considered to be whitelisted, or non-malicious, and we do not want those indicators going out to other systems. For example, a company's own domain name would never need to be blocked.

The whitelisting process creates rules that apply to particular indicators, so that when those indicators come in in the future, they will be automatically whitelisted.

Accessing the Whitelisted Indicator Rules

1. From the navigation menu, click on Threat Library and select **Whitelisting** under the *Data Controls* heading.

The Data Controls page will open with the Whitelisted Indicators tab selected by default.



Creating a Whitelisted Rule



ThreatQ prevents you from creating duplicate whitelist rules through the user interface or an API. If you attempt to do so, the system returns an error message.

From the Whitelisted Indicators Page:

1. Click Add Rule.



The Add Whitelist Rules dialog box opens.



- 2. Select the Indicator type the rule will apply to.
- 3. Add a Rule Value.
- 4. Click Next.

Affected indicators are listed in the dialog box.



5. Review the affected indicators to determine if you are satisfied with the rule.





The rule has not been applied yet, so you still have time to edit it based on whether you are satisfied with how it affects the indicators.

- 6. Click Continue Editing this Rule.
- 7. If you are satisfied with the rule, click **Add Rule**.

The rule is applied to existing indicators, and it is entered into the Whitelisted Rules table.




Any new indicators will also have the rule applied to them as they enter the system.

Editing a Whitelisted Rule

- 1. In the Whitelisted Rules table, locate the rule you wish to edit.
- 2. Click Edit.

The Edit Whitelist Rule dialog box opens.



3. Make the desired edits and click **Next**.



Affected indicators are listed in the dialog box.



4. Review the affected indicators to determine if you are satisfied with the rule.



The rule has not been applied yet, so you still have time to edit it based on whether you are satisfied with how it affects the indicators.

5. If you are satisfied, click **Edit Rule**.

The rule is applied to existing indicators, and it is updated in the Whitelist Rules table.




Any new indicators will also have the rule applied to them as they enter the system.

Removing a Whitelisted Rule

- 1. Locate and select the rule(s) from the Whitelisted Indicators table that you wish to remove.
- 2. Click on the delete Icon



A confirmation dialog box opens, asking if you are sure.



3. Click Delete Whitelist Rule.

The rule be now be removed.



Exports

Exporting is one of the most important ThreatQ features, as it allows you to output nonwhitelisted indicators to an external threat detection system.

ThreatQ provides a number of standard system exports that have previously been identified as useful. You have the option to use those and create your own. ThreatQ Exports are built on the Smarty PHP Template Engine; see https://www.smarty.net/.



A You should NOT attempt to export all of your threat intelligence data with a single export. Attempting to do so will cause system degradation and the export will not complete.




Managing Exports

Accessing the Exports List

1. Select the **Settings** icon >Exports.

The Exports page appears with a table listing all exports in alphabetical order.



Viewing an Export

1. Select the **Settings** icon >Exports.

The Exports page appears with a table listing all exports in alphabetical order.

2. Click the desired URL.

A new tab opens in your browser, and you are taken to the data returned from that export.

The load time may be lengthy depending on the amount of data being returned.

Enabling/Disabling Exports

1. Select the **Settings** Icon >Exports.



The Exports page appears with a table listing all exports in alphabetical order.

- 2. Locate the export you wish to enable/disable.
- 3. Toggle the switch in the On/Off column to enable/disable the export.

A confirmation of your action appears in an alert bar at the top of the page.

Adding an Export

The **Filter by TLP** option will only appear if administrators have enabled TLP viewing. See the Traffic Light Protocol (TLP) topic for more information.

1. Select the **Settings** icon >Exports.

The Exports page appears with a table listing all exports in alphabetical order.

2. Click + Add Export.

The Connection Settings dialog box opens.

- 3. Enter the Export name.
- 4. Verify or edit the token.
- 5. Click Next Step.

The Output Format dialog box opens.

For detailed information on formatting the Output Format dialog box, see Editing an Export's Output Format.

- 6. Select which type of information you would like to export from the first dropdown menu.
- 7. Select the Output type from the second dropdown menu.
- 8. Un-select any of the checkboxes under the **Filter by TLP** section to exclude data by its source TLP classification. All classifications will be selected (included in the export) by default.
- 9. (Optional) Enter special parameters.
- Customize the Output Format Template by putting your cursor where you want the
 variable to go and selecting the variable you'd like to use from the Insert Variable select
 box.
- 11. Verify the information entered.
- 12. Click Save Settings.



The export you just created appears at the bottom of the Exports table, and a confirmation alert appears in an alert bar at the top of the page.

By default, the new export is toggled Off.

Duplicating an Export

Duplicating an export allows you to have a version that you can edit.

1. Select the **Settings** icon >Exports.

The Exports page appears with a table listing all exports in alphabetical order.

- 2. Locate the Export you wish to duplicate.
- 3. Click duplicate in the Actions column.
- 4. The duplicate appears at the bottom of the Exports table. A confirmation of the duplication appears in an alert bar at the top of the page.

By default, the copy you just created is toggled Off.

Editing an Export's Connection Settings

Connection settings are available for each of the exports. The Connection Settings dialog box contains the name of the export as well as the token you'll need to use when connecting a device to ThreatQ.

While you cannot edit or delete any of the exports originally supplied by ThreatQ, you can edit exports you have added to ThreatQ or copies of the original exports.


1. Select the **Settings** Icon > Exports.

The Exports page appears with a table listing all exports in alphabetical order.

- 2. Locate the export you wish to edit.
- 3. Click connection settings in the Connection column.

The Connection Settings dialog box opens.





- 4. Make the desired edits.
- 5. Click Save Settings.

The settings are saved, and a confirmation alert appears in an alert bar at the top of the page.

Editing an Export's Output Format

While you cannot edit or delete any of the exports originally supplied by ThreatQ, you can edit exports you have added to ThreatQ or copies of the original exports.


1. Select the **Settings** Icon > Exports.

The Exports page appears with a table listing all exports in alphabetical order.


- 2. Locate the export you wish to edit.
- 3. Click **output format** in the Output Format column.



The Output Format dialog box opens.



3. Select which type of information you would like to export from the first dropdown menu.



- 4. An admin has the ability to choose between the following options:
 - Adversaries
- Indicators



Attack Pattern
 Intrusion Set

CampaignMalware

• Course of Action • Report

EventsSignatures

Exploit TargetIdentityTTP

Incident
 Vulnerability

5. Select the Output Type from the second dropdown menu.

This sets the content type of the export response to a specific value (e.g. text/plain, text/json). Output Type does not have an impact on how the data is formatted but it does affect the content type within the header of the exported document. For example, if you select Output Type = text/json, when viewing the source of the export, the header will contain a Content Type = text/json attribute.

Please see http://www.w3.org/Protocols/rfc1341/4_Content-Type.html for more information.

- 6. (Optional) Enter special parameters. There are two ways to do this:
 - Adding Special Parameters within ThreatQ One advantage of using this
 option is that the URL for the export remains non-specific and therefore you
 can change what is being exported without having to manage each external
 device individually.
 - Customizing the Output Format Template Choosing this option means you lose the ability to have one place to manage what is being exported.



Details on both methods are detailed in the Output Format Options topic.

Deleting an Export

While you cannot delete any of the exports included with your ThreatQ installation, you can delete any exports you have added or copies of the default exports.

1. Select the **Settings** icon > Exports.

The Exports page appears with a table listing all exports in alphabetical order.



- 2. Locate the export(s) you wish to delete.
- 3. Select one or more exports.
- 4. Click the delete icon at the top right of the Exports table.



Output Format Options

Customizing the Output Format Template

You can customize the output format template for an custom or duplicated export.

1. Select the **Settings icon >Exports**.

The Exports page appears with a table listing all exports in alphabetical order.

- 2. Locate the export for which you want to customize the output format template.
- 3. Click output format.
- 4. In the Output Format dialog box, customize the output format template by putting your cursor where you want the variable to go and selecting the variable you'd like to use from the Insert Variable select box.

This template provides you with the ability to format exactly how your data is printed out within an export.

Important: When formatting your output template, you must wrap all of your declarations within a loop. Please refer to the following as an example:

```
<> {foreach $data as $indicator}

Your variables go here
{/foreach}
```

The Output Format Template is populated based on your selection.

- 5. Verify the information entered.
- 6. Click Save Settings.

Adding Special Parameters

This is where an admin can provide additional parameters to further specify which data will be output via this export. Here are some examples.



TO EXPORT ALL INDICATORS WITH AN ACTIVE STATUS

INDICATOR.STATUS=ACTIVE

To export all CIDR Block indicators that have an active status

Indicator.Status=Active&Indicator.Type=cidr block

To export all CIDR Block indicators and IP Addresses that have an active status

Indicator.Status=Active&Indicator.Type=cidr block&Indicator.Type=ip address

To export all indicators with a score greater than or equal to 7

Indicator.Score>=7

A wide range of filtering parameters are available:

>Indicator

```
<> indicator.type id
   indicator.status id
   indicator.value
   indicator.description
   indicator.hash
   indicator.last detected at
   indicator.expires at
   indicator.expired at
   indicator.touched at
   indicator.deleted at
   indicator.deleted
   indicator.sources count
   indicator.id
   indicator.status
   indicator.type
   indicator.sincedeleted
   indicator.whitelisted *
   indicator.score
   indicator.created at
   indicator.updated at
```



```
indicator.Sources
indicator.Attributes
```

* Using the indicator.whitelisted=Y flag allows whitelisted indicators to be exported. It does not filter indicators by the whitelisted status. For that option, use the indicator.status=whitelistedflag. Additionally, to include only whitelisted indicators in your export, you will need to use both flags:

indicator.status=Whitelisted&indicator.whitelisted=Y

Indicators - Related Objects



1 The following fields are not available for use in the Special Parameters section but can be used in output templates.

```
<> indicator.Indicators
   indicator. Adversaries
   indicator. Events
   indicator. Attachments
   indicator.Signatures
   indicator. Investigations
   indicator. Tasks
   indicator.Campaign
   indicator. Course of action
   indicator. Exploit target
   indicator. Incident
   indicator. Ttp
   indicator.Attack pattern
   indicator. Identity
   indicator. Intrusion set
   indicator.Malware
   indicator.Report
   indicator. Tool
   indicator. Vulnerability
```

> Adversary

```
<> adversary.name
   adversary.touched at
   adversary.deleted at
   adversary.deleted
   adversary.sources count
   adversary.id
   adversary.description
   adversary.created at
```



```
adversary.updated at
adversary.Sources
adversary.Attributes
adversary. Indicators
adversary. Adversaries
adversary. Events
adversary.Attachments
adversary.Signatures
adversary. Investigations
adversary. Tasks
adversary.Campaign
adversary. Course of action
adversary. Exploit target
adversary. Incident
adversary. Ttp
adversary.Attack pattern
adversary. Identity
adversary. Intrusion set
adversary.Malware
adversary.Report
adversary. Tool
adversary. Vulnerability
```

> Event

```
<> event.type id
   event.title
   event.happened at
   event.hash
   event.description
   event.deleted at
   event.deleted
   event.sources count
   event.id
   event.type
   event.touched at
   event.created at
   event.updated at
   event.Sources
   event.Attributes
   event.Indicators
   event.Adversaries
   event. Events
   event.Attachments
   event.Signatures
   event. Investigations
   event.Tasks
   event.Campaign
   event.Course of action
```



```
event.Exploit_target
event.Incident
event.Ttp
event.Attack_pattern
event.Identity
event.Intrusion_set
event.Malware
event.Report
event.Tool
event.Vulnerability
```

> Signature

```
<> signature.description
   signature.hash
   signature.last detected at
   signature.name
   signature.status id
   signature.touched at
   signature.type id
   signature.value
   signature.deleted at
   signature.deleted
   signature.sources count
   signature.id
   signature.status
   signature.type
   signature.created at
   signature.updated at
   signature.Sources
   signature.Attributes
   signature. Indicators
   signature.Adversaries
   signature. Events
   signature.Attachments
   signature.Signatures
   signature. Investigations
   signature. Tasks
   signature.Campaign
   signature. Course of action
   signature. Exploit target
   signature. Incident
   signature. Ttp
   signature.Attack pattern
   signature. Identity
   signature. Intrusion set
   signature.Malware
   signature.Report
```



```
signature.Tool signature.Vulnerability
```

Campaign

```
<> campaign.value
   campaign.status id
   campaign.type id
   campaign.description
   campaign.objective
   campaign.started at
   campaign.ended at
   campaign.deleted at
   campaign.deleted
   campaign.sources count
   campaign.id
   campaign.status
   campaign.type
   campaign.touched at
   campaign.created at
   campaign.updated at
   campaign.Sources
   campaign. Attributes
   campaign. Indicators
   campaign.Adversaries
   campaign. Events
   campaign.Attachments
   campaign.Signatures
   campaign. Investigations
   campaign. Tasks
   campaign.Campaign
   campaign. Course of action
   campaign. Exploit target
   campaign. Incident
   campaign. Ttp
   campaign.Attack pattern
   campaign. Identity
   campaign. Intrusion set
   campaign.Malware
   campaign.Report
   campaign.Tool
   campaign. Vulnerability
```

Course of Action

```
<> course_of_action.value
  course_of_action.status_id
```



```
course of action.type id
course of action.description
course of action.deleted at
course of action.deleted
course of action.sources count
course of action.id
course of action.status
course of action.type
course of action.touched at
course of action.created at
course of action.updated at
course of action. Sources
course of action. Attributes
course of action. Indicators
course of action. Adversaries
course of action. Events
course of action. Attachments
course of action. Signatures
course of action. Investigations
course of action. Tasks
course of action. Campaign
course of action. Course of action
course of action. Exploit target
course of action. Incident
course of action. Ttp
course of action. Attack pattern
course of action. Identity
course of action. Intrusion set
course of action. Malware
course of action. Report
course of action. Tool
course of action. Vulnerability
```

> Exploit

```
<> exploit_target.value
    exploit_target.status_id
    exploit_target.type_id
    exploit_target.description
    exploit_target.deleted_at
    exploit_target.deleted
    exploit_target.sources_count
    exploit_target.id
    exploit_target.status
    exploit_target.type
    exploit_target.type
    exploit_target.created_at
    exploit_target.updated_at
    exploit_target.Sources
```



```
exploit target. Attributes
exploit target. Indicators
exploit target. Adversaries
exploit target. Events
exploit target.Attachments
exploit target. Signatures
exploit target. Investigations
exploit target. Tasks
exploit target.Campaign
exploit target. Course of action
exploit target. Exploit target
exploit target. Incident
exploit target. Ttp
exploit target.Attack pattern
exploit target. Identity
exploit target. Intrusion set
exploit target. Malware
exploit target.Report
exploit target. Tool
exploit target. Vulnerability
```

> Incident

```
<> incident.value
   incident.status id
   incident.type id
   incident.description
   incident.started at
   incident.ended at
   incident.deleted at
   incident.deleted
   incident.sources count
   incident.id
   incident.status
   incident.type
   incident.touched at
   incident.created at
   incident.updated at
   incident.Sources
   incident.Attributes
   incident. Indicators
   incident.Adversaries
   incident. Events
   incident.Attachments
   incident.Signatures
   incident. Investigations
   incident. Tasks
   incident.Campaign
   incident.Course of action
```



```
incident.Exploit_target
incident.Incident
incident.Ttp
incident.Attack_pattern
incident.Identity
incident.Intrusion_set
incident.Malware
incident.Report
incident.Tool
incident.Vulnerability
```

>TTP

```
<> ttp.value
   ttp.status id
   ttp.type id
   ttp.description
   ttp.deleted at
   ttp.deleted
   ttp.sources count
   ttp.id
   ttp.status
   ttp.type
   ttp.touched at
   ttp.created at
   ttp.updated at
   ttp.Sources
   ttp.Attributes
   ttp.Indicators
   ttp.Adversaries
   ttp.Events
   ttp.Attachments
   ttp.Signatures
   ttp.Investigations
   ttp.Tasks
   ttp.Campaign
   ttp.Course of action
   ttp.Exploit target
   ttp.Incident
   ttp.Ttp
   ttp.Attack pattern
   ttp.Identity
   ttp.Intrusion set
   ttp.Malware
   ttp.Report
   ttp.Tool
   ttp.Vulnerability
```



> Attack Pattern

```
<> attack pattern.value
   attack pattern.status id
   attack pattern.type id
   attack pattern.description
   attack pattern.deleted at
   attack pattern.deleted
   attack pattern.sources count
   attack pattern.id
   attack pattern.status
   attack pattern.type
   attack pattern.touched at
   attack pattern.created at
   attack pattern.updated at
   attack pattern. Sources
   attack pattern. Attributes
   attack pattern. Indicators
   attack pattern. Adversaries
   attack pattern. Events
   attack pattern. Attachments
   attack pattern.Signatures
   attack pattern. Investigations
   attack pattern. Tasks
   attack pattern. Campaign
   attack pattern. Course of action
   attack pattern. Exploit target
   attack pattern. Incident
   attack pattern. Ttp
   attack pattern. Attack pattern
   attack pattern. Identity
   attack pattern. Intrusion set
   attack pattern.Malware
   attack pattern. Report
   attack pattern. Tool
   attack pattern. Vulnerability
```

> Identity

```
<> identity.value
   identity.status_id
   identity.type_id
   identity.description
   identity.contact_information
   identity.deleted_at
   identity.deleted
   identity.deleted
   identity.sources_count
   identity.id
```



```
identity.status
identity.type
identity.touched at
identity.created at
identity.updated at
identity.Sources
identity.Attributes
identity. Indicators
identity.Adversaries
identity. Events
identity. Attachments
identity.Signatures
identity. Investigations
identity. Tasks
identity.Campaign
identity. Course of action
identity. Exploit target
identity. Incident
identity. Ttp
identity.Attack pattern
identity. Identity
identity. Intrusion set
identity.Malware
identity.Report
identity.Tool
identity. Vulnerability
```

> Intrusion Set

```
<> intrusion set.value
   intrusion set.status id
   intrusion set.type id
   intrusion set.description
   intrusion set.started at
   intrusion set.ended at
   intrusion set.deleted at
   intrusion set.deleted
   intrusion set.sources count
   intrusion set.id
   intrusion set.status
   intrusion set.type
   intrusion set.touched at
   intrusion set.created at
   intrusion set.updated at
   intrusion set.Sources
   intrusion set.Attributes
   intrusion set. Indicators
   intrusion set. Adversaries
   intrusion set. Events
```



```
intrusion set.Attachments
intrusion set. Signatures
intrusion set. Investigations
intrusion set. Tasks
intrusion set.Campaign
intrusion set. Course of action
intrusion set. Exploit target
intrusion set. Incident
intrusion set. Ttp
intrusion set.Attack pattern
intrusion set. Identity
intrusion set. Intrusion set
intrusion set.Malware
intrusion set.Report
intrusion set. Tool
intrusion set. Vulnerability
```

> Malware

```
<> malware.value
   malware.status id
   malware.type id
   malware.description
   malware.deleted at
   malware.deleted
   malware.sources count
   malware.id
   malware.status
   malware.type
   malware.touched at
   malware.created at
   malware.updated at
   malware.Sources
   malware.Attributes
   malware. Indicators
   malware.Adversaries
   malware. Events
   malware.Attachments
   malware.Signatures
   malware. Investigations
   malware.Tasks
   malware.Campaign
   malware.Course of action
   malware. Exploit target
   malware.Incident
   malware. Ttp
   malware.Attack pattern
   malware. Identity
   malware. Intrusion set
```



```
malware.Malware
malware.Report
malware.Tool
malware.Vulnerability
```

> Report

```
<> report.value
   report.status id
   report.type id
   report.description
   report.deleted at
   report.deleted
   report.sources count
   report.id
   report.status
   report.type
   report.touched at
   report.created at
   report.updated at
   report.Sources
   report.Attributes
   report. Indicators
   report.Adversaries
   report. Events
   report.Attachments
   report.Signatures
   report. Investigations
   report. Tasks
   report.Campaign
   report.Course of action
   report. Exploit target
   report.Incident
   report.Ttp
   report.Attack pattern
   report. Identity
   report.Intrusion set
   report.Malware
   report.Report
   report.Tool
   report. Vulnerability
```

>Tool

```
<> tool.value
  tool.status_id
  tool.type_id
```



```
tool.description
tool.deleted at
tool.deleted
tool.sources count
tool.id
tool.status
tool.type
tool.touched at
tool.created at
tool.updated at
tool.Sources
tool.Attributes
tool. Indicators
tool.Adversaries
tool.Events
tool.Attachments
tool.Signatures
tool. Investigations
tool. Tasks
tool.Campaign
tool.Course of action
tool. Exploit target
tool. Incident
tool. Ttp
tool.Attack pattern
tool. Identity
tool.Intrusion set
tool.Malware
tool.Report
tool.Tool
tool. Vulnerability
```

> Vulnerability

```
vulnerability.value
   vulnerability.type_id
   vulnerability.description
   vulnerability.deleted_at
   vulnerability.deleted
   vulnerability.sources_count
   vulnerability.id
   vulnerability.status
   vulnerability.type
   vulnerability.type
   vulnerability.created_at
   vulnerability.updated_at
   vulnerability.Sources
   vulnerability.Attributes
```



```
vulnerability. Indicators
vulnerability. Adversaries
vulnerability. Events
vulnerability. Attachments
vulnerability.Signatures
vulnerability. Investigations
vulnerability. Tasks
vulnerability.Campaign
vulnerability. Course of action
vulnerability. Exploit target
vulnerability. Incident
vulnerability. Ttp
vulnerability.Attack pattern
vulnerability. Identity
vulnerability. Intrusion set
vulnerability. Malware
vulnerability.Report
vulnerability. Tool
vulnerability. Vulnerability
```

Adding Differential Flags

You can use a differential flag in the Special Parameters section of your export output format to limit the output to new data. This will allow you to include only new data each time the export is run opposed to exporting all data.

Include the following to limit exports to new data only:

```
<> differential=1
```

If you have multiple systems pulling from the same Export, each system should use a unique differential value.



external system 1

https://{tq-host}/api/export/c2ab6df72e67ee13cef90f0e00981b62/? token=npc6z01pFXwfHYb5tm51hMvKQJNYecTG& differential=1

external system 2

https://{tq-host}/api/export/c2ab6df72e67ee13cef90f0e00981b62/? token=npc6z01pFXwfHYb5tm51hMvKQJNYecTG& differential=2



Adding Parameters to the end of the URL

You can append the same parameters listed above to the end of any export URL to achieve the same results. By pursuing this option, you will lose the option of having one place to manage what is being exported via that export.

Using Logical Operators in Export Filters

You can configure exports to output objects matching filter conditions that use logical AND and OR operators. Exports allow the following filters:

- 1. Searching using greater than, less than, or equal to
 - Examples in special parameters string section:

```
<> indicator.score>=5
<> indicator.score<=5</pre>
```

Examples in request URI:

```
<> &indicator.score=>=5
<> &indicator.score=<=8</pre>
```

- 2. Adding multiple criteria for a single field using an OR comparison
 - Example in special parameters string section:

```
<> indicator.score=5&indicator.score=8
```

• Example in request URI:

```
<> &indicator.score[]=5&indicator.score[]=8
```

- 3. Adding multiple criteria for a single field using an AND comparison
 - Example in special parameters string section:



- <> indicator.score>=5&indicator.score<=8</pre>
- Example in request URI:
 - <> &indicator.score[]=>=5&indicator.score[]=<=8</pre>



Output Format Templates

The following section contains templates that you can use to customize an export's output format.

The Output Format Template field for an export is found under its Output Format modal. You can access this by clicking on the **Output Format** link for an export from the main exports page



Important: When formatting your output template, you must wrap all of your declarations within a loop.

Adversaries Template

Events Template

```
{$event.title} ID: {$event.id}

Title: {$event.title}

Type: {$event.type}

Happened: {$event.happened_at}

Description: {$event.description}

Created At: {$event.created}

Updated At: {$event.updated_at}

Touched At: {$event.touched_at}

Deleted At: {$event.deleted_at}

Deleted: {$event.deleted}
```



```
Your variables go here {/foreach}
```

Indicators Template

```
<> {foreach $data as $indicator}
   {$indicator.value}
   ID: {$indicator.id}
   Value: {$indicator.value}
   Type: {$indicator.type}
   Status: {$indicator.status}
   Class: {$indicator.class}
   Description: {$indicator.description}
   Score: {$indicator.score}
   Hash: {$indicator.hash}
   Source Count: {$indicator.sources count}
   Whitelisted: {$indicator.whitelisted}
   Last Detected At: {$indicator.last detected at}
   Created At: {$indicator.created at}
   Updated At: {$indicator.updated at}
   Touched At: {$indicator.touched at}
   Since Deleted: {$indicator.sincedeleted}
   Deleted At: {$indicator.deleted at}
   Deleted: {$indicator.deleted}
   Your variables go here
   {/foreach}
```

Signatures Template



```
Touched At: {$signature.touched_at}
Created At: {$signature.created}
Updated At: {$signature.updated_at}
Deleted At: {$signature.deleted_at}
Deleted: {$signature.deleted}

Your variables go here
{/foreach}
```

Template Variables

The following items are variables that can added to the templates provided above.

Source Variable

```
<> {foreach $adversary.Sources item=source name=Sources}
   {$source.value} {if !empty($source.tlp)}({$source.tlp}){/if}
   {/foreach}
```

Attribute Variable

```
<> {foreach $adversary.Attributes item=attribute name=Attributes}
Name: {$attribute.name}
Value: {$attribute.value}
{/foreach}
```

Adversary Variable

```
<> {foreach $adversary.Adversaries item=adversary name=Adversaries}
Name: {$adversary.name}
Value: {$adversary.value}
{/foreach}
```



Attachment Variable

```
<> {foreach $adversary.Attachments item=attachment name=Attachments}

Name: {$attachment.name}

Value: {$attachment.value}

{/foreach}
```

Event Variable

```
<> {foreach $adversary.Events item=event name=Events}
  Name: {$event.name}
  Value: {$event.value}
  {/foreach}
```

Indicator Variable

```
<> {foreach $adversary.Indicators item=indicator name=Indicators}
  Name: {$indicator.name}
  Value: {$indicator.value}
  {/foreach}
```

Investigation Variable

```
<> {foreach $adversary.Investigations item=investigation
   name=Investigations}
   Name: {$investigation.name}
   Value: {$investigation.value}
   {/foreach}
```

Signature Variable

```
<> {foreach $adversary.Signatures item=signature name=Signatures}
  Name: {$signature.name}
  Value: {$signature.value}
  {/foreach}
```



Task Variable

<> {foreach \$adversary.Tasks item=task name=Tasks}
Name: {\$task.name}
Value: {\$task.value}
{/foreach}



Specific Indicator Exports

The following topics provide instructions on how to export specific indicators for use with an external threat detection system.

See Managing Exports and Output Format Options for more details about configuring exports.

- Cisco TID Exports
- Filelis Exports
- Fortinet Fortigate Exports
- Lancope Exports
- Netwitness Exports
- OpenIOC Signatures Exports
- Palo Alto Exports
- Reservoir Labs Exports
- Splunk Exports
- Symantec ProxySG Exports
- Tenable Exports
- Zeek Exports



Cisco TID Exports

The exports and configurations below enable IOCs to be exported to Cisco TID via the Cisco FMC to be published to Cisco FTD Devices.

The constraints of the Cisco Threat Intelligence Director will only allow the following ThreatQ exports to be used:

- SHA-256
- Domain (FQDN)
- URL
- IPv4
- IPv6
- Email
 - ∘ To
 - From
 - Sender
 - Subject
- 1. Log into your ThreatQ instance.
- 2. Select the **Settings icon >Exports**.

The Exports page appears with a table listing all exports in alphabetical order.

3. Click Add New Export.

The Connection Settings dialog box appears.

- 4. Enter an **Export Name** from the tables listed below.
- 5. Click Next Step.

The Output Format dialog box appears.

- 6. If using TLP, deselect any TLP grade(s) that you do not wish to export.
- 7. Use the tables below to provide the special parameters and output format template:





See the Output Format Options topic for more information on using logical operators in exports.

If a specific score or ranges of scores is required, then the following should be added to the end of the special parameters configuration.

In the example below, this will ensure only IP Address IoCs that are equal to 7 or above are exported.



indicator.status=Active&indicator.deleted=N& indicator.type=IPAddress&indicator.class=network&indicator.score>=7

SHA-256

FIELD	ENTRY
Export Name	Cisco TID – SHA-256
Which type of information would you like to export?	Indicator
Output Type	Text/plain
Special Parameters	indicator.status=Active&indicator.deleted =N&indicator.type=SHA-256
Output Format Template	{foreach \$data as \$indicator} {\$indicator.value} {/foreach}

FQDN

FIELD	ENTRY
Export Name	Cisco TID – FQDN



FIELD	ENTRY
Which type of information would you like to export?	Indicator
Output Type	Text/plain
Special Parameters	indicator.status=Active&indicator. deleted=N&indicator.type=FQDN&indicator.class= network&indicator.score>=11
Output Format Template	{foreach \$data as \$indicator} {\$indicator.value} {/foreach}

URL

FIELD	ENTRY
Export Name	Cisco TID – URL
Which type of information would you like to export?	Indicator
Output Type	Text/plain
Special Parameters	indicator.status=Active &indicator.type=URL& indicator.class=network
Output Format Template	{foreach \$data as \$indicator} {\$indicator.value} {/foreach}

IPv4 Address



FIELD	ENTRY
Export Name	Cisco TID – IPv4
Which type of information would you like to export?	Indicator
Output Type	Text/plain
Special Parameters	indicator.status=Active&indicator.deleted=N&indicator.t ype=IP Address&indicator.class=network
Output Format Template	{foreach \$data as \$indicator} {\$indicator.value} {/foreach}

IPv6 Address

FIELD	ENTRY
Export Name	Cisco TID – IPv6
Which type of information would you like to export?	Indicator
Output Type	Text/plain
Special Parameters	Indicator.Status=Active&Indicator.Type=IPv6 Address
Output Format Template	{foreach \$data as \$indicator} {\$indicator.value} {/foreach}



Email Address

FIELD	ENTRY
Export Name	Cisco TID – Email Address
Which type of information would you like to export?	Indicator
Output Type	Text/plain
Special Parameters Email Address • To • From • Sender	indicator.status=Active&indicator.type=Email Address& indicator.class=network
Output Format Template	{foreach \$data as \$indicator} {\$indicator.value} {/foreach}

8. Click on each of the URL's for the exports. A new browser widow will open displaying the first 10 results, make a note of this URL and the IoCs it is associated with it. The URL is made up off the following sections

```
<> https://<TQ Server>/api/export/<endpoint>/?
limit=10&token=<token>
```

- 9. Remove the limit section and trailing & amp; symbol, examples are below.
 - https://192.168.1.85/api/export/9bc092ce1e318f6c0d10009228729ad6/?
 token=uEyVyzIeYRGBdF2VKcHo9WKYDJvNftSo

This new URL format is needed to configure Cisco TID



- https://192.168.1.85/api/export/9bc092ce1e318f6c0d10009228729ad6/?
 token=uEyVyzIeYRGBdF2VKcHo9WKYDJvNftSo
- 10. Click Save Settings.
- 11. Under **On/Off**, toggle the switch to enable the export.

Cisco FMC Configuration:

- 1. Navigate to the Intelligence director on the Firepower Management Center.
- 2. Choose Intelligence > Sources.
- 3. Click the add icon (+).
- 4. Choose **URL** as the Delivery method for the source.
- 5. Complete the Add Source form.

FIELD	ENTRY
Туре	Flat File
Content	Select a Content type that describes the data contained within the source.
URL	Use the URL format outlined in step 8 of the <i>To export to Cisco TID</i> steps.
Self-Signed Certificate	Toggle the Self-Signed Certificate to active.
Name	Use a descriptive name as we used on the ThreatQ exports. Example: ThreatQ - IP Address
	This will help simplify sorting and handling of incidents based on TID indicators, use a consistent naming scheme across sources.



FIELD	ENTRY
Action	You can either Block or Monitor.
Update Every	Select a time in minutes that the source is to be updated (the minimum is 30 mins, Maximum is 14,400).
TTL	 Specify the number of days for the TTL interval. TID deletes all the source's indicators that are not included in subsequent upload. All observables not referenced by a surviving indicator.

6. Confirm that the **Publish** toggle is set to **Active** if you want to immediately being publishing to elements.



If you do not publish the source at ingestion, you cannot publish all source indicators at once later. Instead, you must publish each observable individually.

7. Click Save.



Fidelis Exports

ThreatQ exports to send indicators of compromise (Email Address, IP Address, MD5, URL and FQDN) to Fidelis Elevate. Elevate has the capability to ingest IOCs from external threat feeds and use them to create rules and policies, and define the reaction by the sensors if such a policy is violated. The exports defined here are in an XML format, although Elevate offers also the option to ingest feed in CSV format.

More details about custom threat feeds and their configuration in Elevate can be found on the help pages of a Fidelis Elevate device: https://<Fidelis Elevate Host or IP>/help/MyWebHelp/Content/FidelisCreatePoliciesHelpVersion/P_InsightCustomFeed.htm

Configuring exports in ThreatQ

Review the Managing Exports topic for a detailed description no how to create and manage exports. If you need further assistance, please open a support ticket with ThreatQ Support.

To export Email Addresses:

- 1. Select the Settings icon > Exports The Exports page appears with a table listing all exports in alphabetical order.
- 2. Click Add New Export The Connection Settings dialog box appears.
- 3. Enter an Export Name
 - Click Next Step
 - The Output Format dialog box appears

Provide the following information:

FIELD	VALUE
Type of information you would like to export?	Indicators
Output type	text/plain



FIELD VALUE

Special Parameters

indicator.status=Active&indicator.
deleted=N&indicator.type=
Email Address&indicator.
class=network&differential=1

Under Output Format Template, enter:

- 4. Click Save Settings
- 5. Under On/Off, toggle the switch to enable the export
- 6. Click on the export URL with the data. Make sure to delete from the URL this parameter limit=10%. The URL should be similar to this one https://<ThreatQ Host>/api/export/ <export ID>/?token=<Authentication Token>

To export IP Addresses:

- 1. Select the Settings icon > Exports The Exports page appears with a table listing all exports in alphabetical order.
- 2. Click Add New Export The Connection Settings dialog box appears.
- 3. Enter an Export Name
 - Click Next Step
 - The Output Format dialog box appears

Provide the following information:



FIELD	VALUE
Type of information you would like to export?	Indicators
Output type	text/plain
Special Parameters	<pre>indicator.status=Active&indicator.delet ed= N&indicator.type=IP Address&indicator. class=network&differential=1</pre>

Under Output Format Template, enter:

- 4. Click Save Settings
- 5. Under On/Off, toggle the switch to enable the export
- 6. Click on the export URL with the data. Make sure to delete from the URL this parameter limit=10&. The URL should be similar to this one https://<ThreatQ Host>/api/export/ <export ID>/?token=<Authentication Token>

To export MD5 hashes:

- 1. Select the Settings icon > Exports The Exports page appears with a table listing all exports in alphabetical order.
- 2. Click Add New Export The Connection Settings dialog box appears.
- 3. Enter an Export Name
 - Click Next Step
 - The Output Format dialog box appears



Provide the following information:

FIELD	VALUE
Type of information you would like to export?	Indicators
Output type	text/plain
Special Parameters	<pre>indicator.status=Active&indicator. deleted=N&indicator.type=MD5& indicator.class=network&differential=1</pre>

Under Output Format Template, enter:

- 4. Click Save Settings
- 5. Under On/Off, toggle the switch to enable the export
- 6. Click on the export URL with the data. Make sure to delete from the URL this parameter limit=10%. The URL should be similar to this one https://<ThreatQ Host>/api/export/ <export ID>/?token=<Authentication Token>

To export FQDNs and URLs:

- 1. Select the Settings icon > Exports The Exports page appears with a table listing all exports in alphabetical order.
- 2. Click Add New Export The Connection Settings dialog box appears.
- 3. Enter an Export Name
 - Click Next Step



The Output Format dialog box appears

Provide the following information:

FIELD	VALUE
Type of information you would like to export?	Indicators
Output type	text/plain
Special Parameters	<pre>indicator.status=Active&indicator.delet ed=N &indicator.type=URL&indicator.type=FQDN & indicator.class=network&differential=1</pre>

Under Output Format Template, enter:

- 4. Click Save Settings
- 5. Under On/Off, toggle the switch to enable the export
- 6. Click on the export URL with the data. Make sure to delete from the URL this parameter limit=10&. The URL should be similar to this one https://<ThreatQ Host>/api/export/ <export ID>/?token=<Authentication Token>

Adding the exports as custom threat feeds in Fidelis Elevate

For a detailed description of the configuration steps, visit the following page on your Fidelis Elevate CommandPost appliance: <a href="https://<Fidelis Elevate Host>/help/MyWebHelp/Content/FidelisCreatePoliciesHelpVersion/P_InsightAddCustomFeed.htm">https://<Fidelis Elevate Host>/help/MyWebHelp/Content/FidelisCreatePoliciesHelpVersion/P_InsightAddCustomFeed.htm.



To add a new feed:

- 1. Go to Policies -> Threat Feeds -> Feed Config and click on Add Feed
- 2. Enter the name of the feed. The entered name must be unique among all custom feeds on CommandPost
- 3. Optional: Add a description that will be displayed in the list of feeds on the Feed Config page
- 4. Select XML as the feed format
- 5. Enter *entry* for the XML format descriptor
- 6. Click the *Add* button
- 7. On the detailed configuration page, enter a Description of the feed
- 8. Select the feed content for the indicator type that is being ingested
- 9. Make sure the following boxes are checked at a minimum
 - Enable
 - Dynamic
 - Verify SSL Certificate
- 10. Select the Refresh Frequency that is needed for the environment
- 11. In the Location (URL) box enter the ThreatQ export URL

Click the *Save* button to save the configuration. To test the feed click on the *Download Now* button



Custom feeds can be set up for a one-time manual upload, manual refresh, or automated refresh.



Fortinet Fortigate Exports

This topic describes the implementation between ThreatQ and the Fortinet FortiGate firewall. The implementation is done using the Threat Feed Connectors feature available in FortiOS v6.0 and above. An export with IOCs is first created on ThreatQ and the export URL is installed FortiGate appliance.



This integration only works on FortiOS v6.0 and above.

Before starting the integration, users are encouraged to familiarize themselves with the following documents:

- Fortinet Fortigate cookbook on blocking malicious domains using threat feeds https://docs.fortinet.com/document/fortigate/6.0.0/cookbook/85580
- Using Threat Feed Connectors in FortiOS v6.0 and above https://help.fortinet.com/ fos60hlp/60/Content/FortiOS/fortigate-security-profiles/Web_Filter/ Overriding%20FortiGuard%20website%20categorization.htm#External
- The Exports section of the ThreatQ Help Center.

Confirm that there is a route between both hosts before you begin the integration between FortiGate and ThreatQ.

Create an Export in ThreatQ

The export is a dynamic list of IOCs which should be configured on ThreatQ and provided to a FortiGate instance to read from. To create an export in ThreatQ follow the steps in the Managing Exports topic.

Use the following information to configure the export:

FIELD	SELECTION
Type of information you would like to export	Indicators
Output Type	text/plain



Special Parameters

There are two options for special parameters:

If security policy of your organization requires that all IP Addresses and FQDNs are sent to FortiGate, use these filters for the special parameters:

<> indicator.status=Active&indicator.
 deleted=N&indicator.type=IP
 Address& indicator.type=FQDN

To send only the IOCs that have a custom status, e.g. Send to FortiGate, use the special parameters below.

To create the custom status:

- 1. Follow the steps in the Indicator Status topic to create a status called **Send to FortiGate**.
- 2. Use the following special parameter:


```
<> indicator.status=Send to
FortiGate
```

Output Template

```
<> {foreach $data as $indicator}
    {$indicator.value}
    {/foreach}
```



Once configured, the export will look similar to the snapshot below.



Configure FortiGate to Download Indicators from ThreatQ



The following detailed steps have been copied from the FortiGate support center and provided here for convenience. The source is https://docs.fortinet.com/document/fortigate/6.0.0/cookbook/85580

Blocking malicious domains using threat feeds

This example uses a domain name threat feed and FortiGate DNS filtering to block malicious domains. The text file in this example is a list of gambling site domain names.

Threat feeds allow you to dynamically import external block lists in the form of a text file into your FortiGate. These text files, stored on an HTTP server, can contain a list of web addresses or domains. You can use threat feeds to deny access to a source or destination IP address in Web Filter and DNS Filter profiles, SSL inspection exemptions, and as a source/destination in proxy policies. You can use Fabric connectors for FortiGate that do not belong to a Fortinet Security Fabric.


1. Create an external block list. The external block list should be a plain text file with one domain name per line. The use of simple wildcards is supported. You can create your own text file or download it from an external service. Upload the text file to the HTTP file server.

```
100casinopicks.com
100kcasino.com
100pour100-gratuit.com
1010casino.com
123gambling.com
123onlinecasino.com
```


- 2. Configure the threat feed:
 - 1. In FortiOS, go to Security Fabric -> Fabric Connectors. Click Create New.
 - 2. Under Threat Feeds, select Domain Name.
 - 3. Configure the Name, URI of external resource, and Refresh Rate fields. In the URI of external resource field, enter the location of the text file on the HTTP file server. By



default, the FortiGate rereads the file and uploads any changes every five minutes.




4. Click View Entries to see the text file's domain list.



- 5. Click OK.
- 3. Add the threat feed to the DNS filter:
 - 1. Go to Security Profiles -> DNS Filter.
 - 2. Scroll to the list of preconfigured FortiGuard filters.



3. The resource file uploaded earlier is listed under Remote Categories. Set the action for this category to Block.



- 4. Configure the outgoing Internet policy:
 - 1. Go to Policy & Objects -> IPv4 Policy.
 - 2. Enable the **DNS Filter** under the *Security Profiles*.
 - 3. From the SSL Inspection dropdown list, select an SSL inspection profile.
- 5. View the results:
 - 1. Visit a domain on the external resource file. This example visits 123gambling.com. A Web Page Blocked! message appears.



2. In FortiOS, go to Log & Report -> DNS Query. The logs show that the 123gambling.com domain belongs to a blocked category.



CNITON



Lancope Exports

These Steps explain how to export Lancope indicators for use with an external threat detection system. Follow the instructions below configure an export for your data.

To export to Lancope:

1. Select the **Settings icon Select the Settings icon Select the Setting icon Select the Se**

The Exports page appears with a table listing all exports in alphabetical order.

2. Click Add New Export.

The Connection Settings dialog box appears.

- 3. Enter an Export Name.
- 4. Click Next Step.

The Output Format dialog box appears.

5. Provide the following information:

FIELD	ENTRY
Which type of information would you like to export?	Indicators
Output Type	text/csv; charset=utf-8
Special Parameters	<pre> <> indicator.status=A ctive&indicator. deleted=N&indicato r.type=IPAddress& indicator.type=CID R Block&indicator.cl ass=network </pre>



```
<> RECORD_NUMBER, GROUP_NAME, GROUP_ID, NETWORK_DEFINITION, PARENT_NA
    MESPACE

0, ThreatQ, -1,,/

{foreach $data as $indicator}

0, "{foreach $indicator.Sources item=source name=Sources}
    {$source.value}{if $smarty.foreach.Sources.last != true}, {/if}
    {/foreach}", -1,
    {$indicator.value|regex_replace:"/[\r\t\n]/":""|
    replace:"\"":""}, "/ThreatQ/"

{/foreach}
```

- 6. Click Save Settings.
- 7. Under **On/Off**, toggle the switch to enable the export.



Netwitness Exports

This topic explains how to export Netwitness indicators for use with an external threat detection system. Follow the instructions below to export your data for:

- Netwitness FQDN
- Netwitness IP

To export to Netwitness FQDN:

1. Select the **Settings icon Sexports**.

The Exports page appears with a table listing all exports in alphabetical order.

2. Click Add New Export.

The Connection Settings dialog box appears.

- 3. Enter an **Export Name**.
- 4. Click Next Step.

The Output Format dialog box appears.

5. Provide the following information:

FIELD	ENTRY
Which type of information would you like to export?	Indicators
Output Type	text/csv; charset=utf-8
Special Parameters	<pre> <> indicator.status</pre>



Under Output Format Template, enter:

```
<> {foreach $data as $indicator}

"{$indicator.value}","{foreach $indicator.Sources as $source}
{$source.value},

{foreachelse}{/foreach}","https://{$http_host}/indicators/
{$indicator.id}/details"

{/foreach}
```

- 6. Click **Save Settings**.
- 7. Under **On/Off**, toggle the switch to enable the export.

To export to Netwitness IP:

1. Select the **Settings icon** ■ **>Exports**.

The Exports page appears.

2. Click Add New Export.

The Connection Settings dialog box appears.

- 3. Enter an **Export Name**.
- 4. Click Next Step.

The Output Format dialog box appears.

5. Provide the following information:

FIELD	ENTRY
Which type of information would you like to export?	Indicators
Output Type	text/csv; charset=utf-8



Special Parameters

<> indicator.status=Act
 ive&indicator.
 deleted=N&indicator.
 type=IP
 Address&indicator.cl
 ass=network

```
<> {foreach $data as $indicator}

"{$indicator.value}","{foreach $indicator.Sources as $source}
    {$source.value}, {foreachelse} {/foreach}", "https://
    {$http_host}/indicators/{$indicator.id}/details"
    {/foreach}
```

- 6. Click **Save Settings**.
- 7. Under **On/Off,** toggle the switch to enable the export.

CNITON



OpenIOC Signature Exports

This topic explains how to export OpenIOC signatures for use with an external threat detection system. Follow the instructions below to export your data.

To export to OpenIOC CSV:

1. Select the **Settings icon Select the Settings icon Select the Setting icon Select the Se**

The Exports page appears with a table listing all exports in alphabetical order.

2. Click Add New Export.

The Connection Settings dialog box appears.

- 3. Enter an Export Name.
- 4. Click Next Step.

The Output Format dialog box appears.

CICL D

5. Provide the following information:

FIELD	ENIRY
Which type of information would you like to export?	Signatures
Output Type	text/csv
Special Parameters	<pre><> signature.status</pre>

```
<> {foreach $data as $signature}

"{$signature.name|replace:'"':'\"'}","{$signature.value|
```



```
replace:'"':'\"'}"
{/foreach}
```

- 6. Click **Save Settings**.
- 7. Under **On/Off**, toggle the switch to enable the export.



Palo Alto Exports

1. Select the **Settings icon** Sexports.

The Exports page appears with a table listing all exports in alphabetical order.

2. Click Add New Export.

The Connection Settings dialog box appears.

- 3. Enter an **Export Name**.
- 4. Click Next Step.

The Output Format dialog box appears.

5. Provide the following information:

FIELD	ENTRY
Which type of information would you like to export?	Indicators
Output Type	text/plain
Special Parameters	<pre> <> indicator.status</pre>

```
<> {foreach $data as $indicator}
     {$indicator.value}

*.{$indicator.value}
```



{/foreach}

- 6. Click **Save Settings**.
- 7. Under **On/Off**, toggle the switch to enable the export.

Palo Alto: PANOS and Panorama Exports

This topic describes the implementation between ThreatQ and Palo Alto firewall. The implementation is done using Palo Alto's External Dynamic List (EDL) functionality. An export with IOCs is first created on ThreatQ and the export URL is provided to Palo Alto as an EDL. The following details go over the steps to create, and add the EDL to ThreatQ.

Prerequisites

Before you begin the integration between Palo Alto and ThreatQ, confirm that there is a route between both hosts.

Create an export in ThreatQ

The export is a dynamic list of IOCs which should be configured on ThreatQ and provided to a Palo Alto instance to read from.

The following link lists the guidelines for the format of the export list in ThreatQ.

There are separate guidelines for IP, FQDN and URL lists.

These guidelines are both for PANOS and Panorama.:

https://docs.paloaltonetworks.com/pan-os/9-0/pan-os-admin/policy/use-an-external-dynamic-list-in-policy/formatting-guidelines-for-an-external-dynamic-list.html

Configure an External Dynamic List (EDL) in PANOS

To add the dynamic list to Palo Alto, follow the instructions from here.


https://docs.paloaltonetworks.com/pan-os/9-0/pan-os-admin/policy/use-an-external-dynamic-list-in-policy/configure-the-firewall-to-access-an-external-dynamic-list.html

Configure an External Dynamic List (EDL) in Panorama


1. Navigate to **Device Groups > Objects**, and then click on the **External Dynamic List** in the left pane, about half way down.



2. Add a new dynamic list by clicking on the **Add** button at the bottom of the screen.



3. Provide a Name, Type, and for source provide the ThreatQ exports URL.



4. Click OK.

Retrieve an External Dynamic List from the Source

Once the list has been configured you can retrieve the indicators from that list.

Follow the steps from here: https://docs.paloaltonetworks.com/pan-os/9-0/pan-os-admin/policy/use-an-external-dynamic-list-in-policy/retrieve-an-external-dynamic-list-from-the-web-server.html

Enforce Policy on an External Dynamic List

To create a policy to enforce rules for the indicators from the EDL, follow the steps from here: https://docs.paloaltonetworks.com/pan-os/9-0/pan-os-admin/policy/use-an-external-dynamic-list-in-policy/enforce-policy-on-an-external-dynamic-list.html



Reservoir Labs Exports

This topic explains how to export Reservoir Labs indicators for use with an external threat detection system. Follow the instructions below to export your data.

To export to Reservoir Labs:

1. Select the **Settings icon Select the Settings icon Select the Setting icon Select the Se**

The Exports page appears with a table listing all exports in alphabetical order.

2. Click Add New Export.

The Connection Settings dialog box appears.

- 3. Enter an Export Name.
- 4. Click Next Step.

The Output Format dialog box appears.

5. Provide the following information:

FIELD	ENTRY
Which type of information would you like to export?	Indicators
Output Type	text/plain
Special Parameters	<pre><> indicator.status</pre>

```
     * #fields{$tab}indicator{$tab}indicator_type{$tab}
     meta.source{$tab}meta.url

     {foreach $data as $indicator}
}
```



```
{if $indicator.type eq "CIDR Block"}{continue}{/if}
{if $indicator.type eq "SHA-1"}{continue}{/if}
{if $indicator.type eq "SHA-256"}{continue}{/if}
{if $indicator.type eq "SHA-384"}{continue}{/if}
{if $indicator.type eq "SHA-512"}{continue}{/if}
{\$indicator type=""}
{$source found=0}
{if $indicator.type eq "IP Address"}
{\$indicator type="Intel::ADDR"}{\if}
{if $indicator.type eq "URL"}
{\$indicator type="Intel::URL"}{\if}
{if $indicator.type eq "Email Address"}
{\$indicator type="Intel::EMAIL"}{/if}
{if $indicator.type eq "FQDN"}
{\$indicator type="Intel::DOMAIN"} {\/if\}
{if $indicator.type eq "MD5"}
{\$indicator type="Intel::FILE HASH"}{\/if}
{if $indicator.type eq "Filename"}
{\$indicator type="Intel::FILE HASH"}{\if}
{if $indicator type ne ""}
{$indicator.value}{$tab}{$indicator type}{$tab}{foreach
$indicator.Sources item=source name=Sources}{if
$smarty.foreach.Sources.first == true}
{\$source.value} {\$source found=1} {\/if\} {\/foreach\} {\/if\}
source found == 0}-{/if}
{\$tab}https://{\$http host}/indicators/{\$indicator.id}/
details
{/if}
{/foreach}
```

6. Click **Save Settings**.



7. Under **On/Off**, toggle the switch to enable the export.



Splunk Exports

This topic explains how to export indicators for use with an external threat detection system. Follow the instructions below to export your data.

To export to Splunk:

1. Select the **Settings icon Select the Settings icon Select the Setting icon Select the Se**

The Exports page appears with a table listing all exports in alphabetical order.

2. Click Add New Export.

The Connection Settings dialog box appears.

- 3. Enter an Export Name.
- 4. Click Next Step.

The Output Format dialog box appears.

5. Provide the following information:

FIELD	ENTRY
Which type of information would you like to export?	Indicators
Output Type	text/plain
Special Parameters	<pre><> indicator.sinced eleted=Y</pre>

Under Output Format Template, enter:

<> #indicator{\$tab}indicator_type{\$tab}last_modified{\$tab}
reference_url{\$tab}source{\$tab}campaign{\$tab}status

{foreach \$data as \$indicator}



```
{$indicator.value}{$tab}{$indicator.type}
{$indicator.updated_at}

{$tab}https://{$http_host}/indicators/{$indicator.id}/
details{$tab}{foreach $indicator.Sources item=source
name=Sources}{$source.value}{if $smarty.foreach.Sources.last
== false}, {/if}{/foreach}{$tab}{foreach
$indicator.Adversaries item=adversary name=Adversaries}
{$adversary.value}{if $smarty.foreach.Adversaries.last ==
false}, {/if}{/foreach}{$tab}{$indicator.status}

{/foreach}
```

- 6. Click Save Settings.
- 7. Under **On/Off**, toggle the switch to enable the export.



Symantec ProxySG Exports

This topic describes the implementation between ThreatQ and the Symantec ProxySG appliance. The implementation is done using the Local Database Content Filtering functionality available in the ProxySG. An export with IOCs is first created on ThreatQ and the export URL is installed on the proxy.

Before starting the integration, users are encouraged to familiarize themselves with the following documents:

- Symantec ProxySG CLI: https://symwisedownload.symantec.com/resources/sites/SYMWISE/content/live/ DOCUMENTATION/10000/DOC10456/en_US/6.7CLI.pdf? __gda__=1582794846_0c0b5ae73454290ea953391b8aa5f508
- Local Content Filtering Database: https://origin-symwisedownload.symantec.com/resources/webguides/ managementcenter/2.0.1.1/Content/ConfigurationManagementGuide/6_Policy/local_db.htm

Before you begin the integration between Symantec ProxySG and ThreatQ, confirm that there is route between both hosts.

Create an Export in ThreatQ

The export is a dynamic list of IOCs which should be configured on ThreatQ and provided to a ProxySG instance to read from. To create an export in ThreatQ follow the steps in the Adding an Export topic on the ThreatQ Help Center.

The export script should be the following. This will strip the port and URL path from the IOCs.

```
<> define category threatq_iocs
  {foreach $data as $indicator}
  {assign var=parts value="/"|explode:$indicator.value}
  {assign var=hostname value=":"|explode:$parts[2]}
  {assign var=fqdn value=":"|explode:$parts[0]}
  {if $fqdn[0] eq "http" or $fqdn[0] eq "https"}
  {assign var=domain value=$hostname[0]}
  {else}{assign var=domain value=$fqdn[0]}{/if}
  {$domain}
  {/foreach}
  end
```



Configure ProxySG to Download Indicators from ThreatQ

There are two methods to install the dynamic list in the ProxySG -

- via the Management Console
- via the Proxy's CLI

The management console UI can accept only a single block list. Starting with ProxySG v6.7.4, you can configure the proxy to read from up to seven dynamic lists. The following two sections go over the methods for installing dynamic block lists.

Via the Management Console

- 1. Open the ProxySG management console.
- 2. Navigate to Configuration > Content Filtering Local Database.

The following screen will load.



3. Insert the **export URL** from TQ in the **URL** space and click on the **Download now** button.

This will initiate a pull of the indicators from the ThreatQ into the proxy. To check on the status of the download, click on **View Download Status**. Any download related messages will be shown in the download status window.

Via the ProxySG CLI

In addition to the Management Console UI, the proxy has a CLI which provides more configuration options. In the reference section at the end of this document, you can find a PDF document with the CLI commands. To help with testing of the integration below is a sequence



of commands that allows a user to install the exports from ThreatQ in a local content database on the proxy.

1. Log into the Blue Coat CLI:



- Use the password set in the initial configuration.
- 2. Enable the admin mode:
 - <> enable
 - 1 You will be prompted for a password which is usually the account password.
- 3. Enter the following command access the config model of the appliance.
 - <> config
- 4. Select **TERMINAL** at the prompt.
- 5. Start working with the content filtering database:
 - <> content-filter
- 6. Enter the Local Content Filtering DB mode.
 - <> local
- 7. Create a new database name if needed.
 - <> create tq_test
- 8. Enter db edit mode to download the URL.
 - <> edit tq test
- 9. Bind the URL of the ThreatQ export to the content database on the ProxySG.
 - A Put double quotes around the URL.
 - <> download url "https://<TQ>/api/export/<hash>/?
 limit=1000&token=<token>"
- 10. Download the database now.



- <> download get-now
- 11. View the status of the current, and older, download
 - <> view
- 12. Show the contents of the downloaded local database file.
 - <> source
- 13. If you want to configure auto downloads there are various options available. To list all the download options use the following command
 - <> download ?


Create and Install a Content Filtering Policy

The final step is to install a content filtering policy using the indicators from the ThreatQ export which are being downloaded to a content filtering database on the proxy.

- 1. Open ProxySG (the example here uses the virtual proxy appliance).
- 2. Navigate to Configuration Policy > Visual Policy Manager and click on Launch Java VPM.




3. From within the VPM, create a new **Web Access Layer** by navigating to **Policy Add > Web Access Layer**.





- 4. Assign a name for the new layer, and after it's created right click on the **Destination object** and select **Set**.
- 5. Under the drop down in the modal window select **All (sort by object name)** and then click on **Edit** in the lower right corner.



This will open a new window, in which you can select all the categories to be blocked by the ProxySG appliance. The list of URLs exported from ThreatQ will be available under the Local category.

6. Expand **Local** and select the name you've given the export from ThreatQ. In this example, the name is **tq_malicious_url**.




- 7. Click **OK**, and then again **OK** to go back to the **VPM**.
- 8. Highlight the newly created policy layer, and click on the **Install policy** button in the upper right corner.



A

Before installing the policy, make sure that the type of **Action** on the policy is **Deny**. If it shows **Allow**, make sure to change it to **Deny**. The action instruction what type action ProxySG should enforce when it detects that a user sends a request to any of the indicators in the list exported from ThreatQ.



9. The new policy is now installed and any active indicators exported from ThreatQ will be blocked by the ProxySG.



Tenable Exports

This topic explains how to export Tenable indicators for use with an external threat detection system. Follow the instructions below to export your data for:

- Tenable FQDN
- Tenable IP Address
- Tenable MD5 Address

To export to Tenable FQDN:

1. Select the **Settings icon Sexports**.

The Exports page appears with a table listing all exports in alphabetical order.

2. Click Add New Export.

The Connection Settings dialog box appears.

- 3. Enter an Export Name.
- 4. Click Next Step.

The Output Format dialog box appears.

- 5. Provide the following information:
 - For Which type of information would you like to export? Choose Indicators.
 - For **Output type**, choose text/plain.
 - Under **Special Parameters**, enter:

indicator.status=Active&indicator.deleted=N&indicator.type=FQDN&indicator.class=networld

```
{foreach $data as $indicator}

{$indicator.value},{foreach $indicator.Sources item=source name=Sources}

{$source.value}{if $smarty.foreach.Sources.last == false}/{/if}{/foreach}

{/foreach}
```



- 6. Click Save Settings.
- 7. Under **On/Off**, toggle the switch to enable the export.

To export to Tenable IP Address:

- 1. Select the **Settings icon Select Select Select Settings Select Select**
- 2. The Exports page appears.
- 3. Click Add New Export.
- 4. The Connection Settings dialog box appears.
- 5. Enter an **Export Name**.
- 6. Click Next Step.
- 7. The Output Format dialog box appears.
- 8. Provide the following information:
 - For Which type of information would you like to export? Choose Indicators.
 - For Output type, choose text/plain.
 - Under **Special Parameters**, enter:

indicator.status=Active&indicator.deleted=N&indicator.type=IP Address&indicator.class=network

• Under Output Format Template, enter:

```
{foreach $data as $indicator}

{$indicator.value},{foreach $indicator.Sources item=source name=Sources}

{$source.value}{if $smarty.foreach.Sources.last == false}/{/if}{/foreach}

{/foreach}
```

- 9. Click Save Settings.
- 10. Under **On/Off**, toggle the switch to enable the export.

To export to Tenable MD5 Address:

1. From the navigation menu, choose the **gear icon > Exports**.

The Exports page appears.

2. Click **Add New Export**.



The Connection Settings dialog box appears.

- 3. Enter an Export Name.
- 4. Click Next Step.
- 5. The Output Format dialog box appears.
- 6. Provide the following information:

FIELD ENTRY

Which type of information would you like to export?	Indicators
Output Type	text/plain
Special Parameters	<pre> <> indicator.status</pre>

```
<> {foreach $data as $indicator}

    {$indicator.value}, {foreach $indicator.Sources item=source
    name=Sources}

    {$source.value}{if $smarty.foreach.Sources.last == false}/{/
    if}{/foreach}

    {/foreach}
```

- 7. Click **Save Settings**.
- 8. Under **On/Off**, toggle the switch to enable the export.



Zeek Exports



Bro is now known as Zeek.

These steps explain how to export Zeek indicators for use with an external threat detection system. Follow the instructions below to export your data.

1. Select the **Settings icon Select the Settings icon Select the Setting icon Select the Select the Setting icon S**

The Exports page appears with a table listing all exports in alphabetical order.

2. Click **Add New Export**.

The Connection Settings dialog box appears.

- 3. Enter an **Export Name**.
- 4. Click Next Step.

The Output Format dialog box appears.

5. Provide the following information:

Which type of information would you like to export? Indicators

Output Type	text/plain
Special Parameters	

<> indicator.status
=Active&indicato
r.deleted=N

```
<> #fields{$tab}indicator{$tab}indicator_type{$tab}
   meta.source{$tab}meta.url
   {foreach $data as $indicator}
   {$indicator_type=""}
```



```
{$source found=0}
{if $indicator.type eq "CIDR Block"}
{\$indicator type="Intel::SUBNET"}{\if}
{if $indicator.type eq "IP Address"}
{\$indicator type="Intel::ADDR"}{/if}
{if $indicator.type eq "URL"}{$indicator type="Intel::URL"}{/
if}
{if $indicator.type eq "Email Address"}
{\$indicator type="Intel::EMAIL"}{\if}
{if $indicator.type eq "FQDN"}
{\$indicator type="Intel::DOMAIN"}{/if}
{if $indicator.type eq "MD5"}
{\$indicator type="Intel::FILE HASH"}{/if}
{if $indicator.type eq "SHA-1"}
{\$indicator type="Intel::FILE HASH"}{\if}
{if $indicator.type eq "SHA-256"}
{\$indicator type="Intel::FILE HASH"}{\/if}
{if $indicator.type eq "SHA-256"}
{\$indicator type="Intel::FILE HASH"}{\if}
{if $indicator.type eq "SHA-384"}
{\$indicator type="Intel::FILE HASH"}{\/if}
{if $indicator.type eq "SHA-512"}
{\$indicator type="Intel::FILE HASH"}{\if}
{if $indicator.type eq "Filename"}
{\$indicator type="Intel::FILE_HASH"}{\if}
{if $indicator type ne ""}
{$indicator.value}{$tab}{$indicator type}{$tab}{foreach
$indicator.Sources item=source name=Sources}{if
$smarty.foreach.Sources.first == true}
{$source.value}{$source found=1}{/if}{/foreach}{if
source found == 0}-{/if}
{$tab}https://{$http host}/indicators/{$indicator.id}/details
{/if}
```



{/foreach}

- 6. Click **Save Settings**.
- 7. Under **On/Off**, toggle the switch to enable the export.




Integrations Management



ThreatQuotient does not issue API keys for third-party vendors. Contact the specific vendor to obtain API keys and other integrated-related credentials.

The My Integrations page allows you to add, remove, and configure feeds, custom connectors, and operations that you have downloaded from the ThreatQ Marketplace or are seeded in ThreatQ.



From the My Integrations page, you can view all integrations installed on your ThreatQ instance.

There are several filters available that allow you to narrow down your integrations. The platform will remember your filter selections for the duration of your session. These filters include:

FILTER DETAILS

Keyword Filter the integrations list by keyword.



Type

Filter the integrations list by integration type. Options include:

- Intelligence Feeds and Connectors
- Operations

Category

Filter the list by the category of integration: Labs, Commercial, OSINT, STIX/TAXII.

Status (All/Enabled/ Disabled tabs)

Filter the list of installed integrations by status: enabled or disabled. A count of integrations appears next to each tab and reflects any filter that is selected.




The **All** tab, which displays both enabled and disabled integrations, is selected by default.

Clear Search Filters Clears the current search filters that are currently in use.

Accessing Integrations Management

- 1. Navigate to your ThreatQ instance.
- 2. Click on the **Integrations** option in the main navigation and select one of the following options:




MENU OPTION

DETAILS



Marketplace	Opens the ThreatQ Marketplace in a new tab.
My Integrations	Opens the My Integrations page.
Feeds and Connectors	Opens the My Integrations page filtered to only display feeds and connectors.
Operations	Opens the My Integrations page filtered to only display operations.

The My Integrations page will load based on your selection. All integrations currently installed on your platform, both enabled and disabled, can be found on this page. The **All** status tab will be selected by default.





Integration Types

ThreatQ integrations include threat intelligence feeds, custom connectors, and operations. This topic will highlight specific information about each type of integration.



Custom connectors typically fall under the **Labs** category of Threat Intelligence Feeds.

Threat Intelligence Feed Categories

Threat Intelligence feeds are organized into the following categories:

CATEGORY	DETAILS
Commercial	Commercial feeds are provided by paid feed providers as a service. To enable these feeds in ThreatQ, you will need an API ID or API Key from the provider. Commercial feeds typically provide highly contextual threat intelligence data. You can learn more about these feeds on their vendor's websites.
OSINT or Open Source	OSINT feeds are open source threat intelligence feeds. Open source feeds are free to use, but some may require you to register with the feed provider to attain an API Key.
STIX/TAXII	STIX stands for Standard Threat Information Expression, it is an emerging standard for the sharing of machine readable intelligence and incident data. A STIX package is an XML document that can contain many indicators and related context information. For the automated sharing of STIX packages, a protocol called TAXII (Trusted Automated eXchange of Indicator Information) is used to provide a feed to consumers. ThreatQ provides a feature for consuming STIX/Taxii feeds.
Labs	Labs are driven by ThreatQuotient's Threat Intelligence Services Team. Labs feeds provide a solution for data ingestion that is not provided by the feeds pre-configured with the ThreatQ platform. You should inquire with a Threat Intelligence Engineer to see what Labs are available.



Operations

Operations enhance your threat intelligence data by allowing you to add attributes, as well as related indicators, from third party security services, both commercial and open source. You accomplish this by creating objects to connect to a desired service, receive threat intelligence, and display that threat intelligence in ThreatQ.

To develop custom operations, you should possess a basic functional knowledge of Python version 3 development.

ThreatQ operations are written in Python v3.5.5. We recommend allocating a non-production ThreatQ appliance for Operations development. You may use this development appliance to troubleshoot your operations before deploying them to production. You may also set up a local Python environment, write your script, and then copy it onto your ThreatQ appliance.



Managing Integrations

You can add/remove, enable/disable, and configure integrations from the My Integrations page.



ThreatQuotient does not issue API keys for third-party vendors. Contact the specific vendor to obtain API keys and other integrated-related credentials.

Steps may slightly differ depending on the individual integration. Refer to the integration's individual guide for specific details.

Adding Integrations




ThreatQuotient does not issue API keys for third-party vendors. Contact the specific vendor to obtain API keys and other integrated-related credentials.

You can add integrations using the My Integration page. The steps for upgrading an integration are the same as adding an integration.




Some custom connectors cannot be installed via the ThreatQ UI. See your connector's documentation for specific installation steps.

- 1. Log into https://marketplace.threatq.com.
- 2. Locate and download the desired integration file.
- 3. Navigate to your ThreatQ instance.
- 4. Click on the **Integrations** option in the main navigation and select **My Integrations**.






5. The My Integrations page will load. All integrations currently installed on your platform, both enabled and disabled, can be found on this page. The **All** tab will be selected by default.



6. Click on the Add New Integration button located to the top-right of the page.



The Add New Integration dialog box will open with the **Add New Integration** option select by default.




- 7. Upload the integration file using one of the following methods:
 - $\,{}^{\circ}\,$ Drag and drop the integration file into the dialog box
 - Select Click to Browse to locate the integration file on your local machine



ThreatQ will inform you if the integration already exists on the platform and will require user confirmation before proceeding. ThreatQ will also inform you if the new version of the integration contains changes to the user configuration. The new user configurations will overwrite the existing ones for the integration and will require user confirmation before proceeding.



8. If the integration file contains multiple feeds, you will be prompted to select which feeds to install. Select the feeds to include and click on **Install**.



The integration will now be installed on the platform. You will still need to configure and enable the integration before it can be used.




Adding STIX/TAXII Integrations




ThreatQuotient does not issue API keys for third-party vendors. Contact the specific vendor to obtain API keys and other integrated-related credentials.

1. Click on the Integrations option in the main navigation and select My Integrations.




The My Integrations page will load. All integrations currently installed on your platform, both enabled and disabled, can be found on this page. The Enabled tab will be selected by default.



2. Click on the Add New Integration button located to the top-right of the page.




The Add New Integration dialog box will open with the **Add New Integration** option select by default.



3. Click on the Add New TAXII Feed option.



The Add TAXII Feed form will load.



4. Complete the following fields:



FIELD	INSTRUCTIONS
What would you like to name this feed?	Enter the feed's name that will be displayed throughout ThreatQ. The name must be at least 5 characters long It does not need to match the Collection Name .
How often would you like to pull new data from this feed?	Choose Every Hour or Every Day .
TAXII Connection Settings	
TAXII Server Version	Options include: 1.0, 1.1, 2.0. This field is required.
Discovery URL	This is where the TAXII server can be reached. This field is required.
Poll URL	An optional URL that specifies a specific endpoint on the TAXII Server to poll for data.
Collection Name	The name of the collection of data in the feed you will access. This field is required.
Client User Authentication	



FIELD	INSTRUCTIONS
Username	Enter a username if required for the feed.
Password	Enter a password if required for the feed.
Client TLS/SSL Authentication	
Client Certificate	Enter a certificate if required for the feed.
Client Key	Enter a private key if required for the feed.
Server Authentication	
Verify SSL	Leave the checkbox checked to require that the TAXII client verify the provider's SSL certificate.
Host CA Certificate Bundle	The provider's CA Certificate used to verify SSL. The Host CA Certificate Bundle will not be honored if the Verify SSL option is not selected.

5. Click on **Add TAXII** Feed.


The TAXII/STIX feed will be added to the Integrations page. You will still need to configure and enable the integration.




Configuring an Integration

The integration must already be installed in order to access it's configuration. See the Adding Integrations topic for more details.

1. Click on the Integrations option in the main navigation and select My Integrations.




The My Integrations page will load. All integrations currently installed on your platform, both enabled and disabled, can be found on this page. The **All** tab will be selected by default.





2. Locate and click on the integration to load its details page.

Cybercrime Tracker



The integration details page will load. Integration details, such as the author, required ThreatQ version and targeted object types will be listed to the left. The **Configuration** and **Activity Log** (if the integration is a feed) will be listed to the right. If the integration is a feed, the **Activity Log** will load after the initial run.

3. Enter the integration's required configuration parameters and then click on Save.



For feeds and some connectors, you can configure feed run frequency and default object status (if the object is an indicator or signature). Refer to the integration's user guide for more details. For instructions on performing a manual feed run - see Performing Manual Runs (feeds).

You can also enable feed health notifications for that specific feed. See the Feed Health Notifications for more information.

4. Click on the **Enable/Disable** toggle switch to enable the integration.



After being enabled, the Feed will automatically start a run.


The integration has now been configured and enabled for use.



Feed Health Notifications


Feed Health Notifications allows the ThreatQ application to send you, and other designated users, email and in-app notifications when a feed encounters an issue.

The in-app notifications will appear in Notification Center for users with an administrator or maintenance account. These notifications include a link that redirects you to the Activity tab on the configuration page for the integration.





The emails, sent to users designated on the Notification Settings page, will contain useful information such as connection information, data ingested, and an ingestion summary.



See the Notification Settings topic for more information.




Enabling/Disabling Integrations

You can enable and disable installed integrations for an integration's details page. Disabling an integration allows you deactivate an integration without completely removing it from your instance.




The integration must already be installed in order to access it's configuration. See the Adding Integrations for more details.

1. Click on the Integrations option in the main navigation and select My Integrations.




The My Integrations page will load. All integrations currently installed on your platform, both enabled and disabled, can be found on this page. The **All** tab will be selected by default.






2. Locate and click on the integration to load its details page.



The integration details page will load. Integration details, such as the author, required ThreatQ version and targeted object types will be listed to the left. The **Configuration** and **Activity Log** (if the integration is a feed) will be listed to the right. If the integration is a feed, the **Activity Log** will load after the initial run.

3. Click on the **Enable/Disable** toggle switch to either enable or disable the integration.

Enabled integrations will have a green header and an **Enabled** banner on the My Integrations page.







Removing an Integration

Removing an integration will uninstall an integration for your instance. All previously ingested data will remain in the system. You can also disable an integration, which will deactivate it without completely removing the integration from your instance.

1. Click on the **Integrations** option in the main navigation and select **My Integrations**.





The My Integrations page will load. All integrations currently installed on your platform, both enabled and disabled, can be found on this page. The **All** tab will be selected by default.






2. Locate and click on the integration to load its details page.





3. Click on the Uninstall button located below the Enable/Disable toggle.

The Uninstall dialog box will open asking you to confirm the uninstall selection.



4. Click on **Uninstall** to confirm and remove the integration.




Performing Manual Runs (feeds)




Not every feed integration allows users to perform a manual run.

To initiate a manual feed integration run:

1. Click on the Integrations option in the main navigation and select My Integrations.




The My Integrations page will load. All integrations currently installed on your platform, both enabled and disabled, can be found on this page. The **All** tab will be selected by default.






2. Locate and click on the integration to load its details page.

< MITRE PRE-ATT&CK






- 3. Confirm that the integration is enabled.
- 4. Click on the Run Integration button located beneath Enable/Disable toggle switch.
 - If the Run Integration button is not visible, the integration does not support manual runs.




The Trigger Manual Run dialog box will open.



- 5. Select a **Start Date**, **Start Time**, and **Time Zone** for your run.
- 6. Select an **End Date**, **End Time**, and **Time Zone** for your run.

Some feed integrations only support a **Start Date**.



7. Click on Queue Run.

Running an Operation Integration

Depending on the operation, steps may differ based on the individual operation. See the operation's individual user guide for specific details.




Operations are designed to work with specific object types and sub-types. The operation's details page provides you with list of object types that work with operation.

Emerging Threats Configuration Api Key • ☐ Bypass system proxy configuration for this operation Disabled Enabled Additional Information Integration Type: Operation Author: ThreatQ Description: Enrichment data from Emerging Threats IQRisk Version: 1.0.1 Required ThreatQ Version: 2.1 Works With: Indicator FODN IP Address

- 1. Navigate to the Threat Library and locate a system object your operation works with.
- 2. Click on the object to access it's details page.
- 3. Scroll down to the *Operations* pane on the details page.

You can also click on the Operations heading located in the left-hand menu to jump the operations pane.

A list of available operations will be listed in the pane.





4. Click on an operation to run it.



Integration-Related Commands


The following integration-related commands can be found in the Command Line Interface (CLI) section:

- Add/Update a CDF
- Source Consolidation
- Source Merge
- View Feed Queues
- Historic Feed Pulls
- iSight Historic Feed Pulls
- TIS Custom Connector Historic Feed Pulls



Activity Log (feeds)

The Activity Log provides you with details regarding recent runs performed by an feed integration.




Log Details include run details that include:

LOG DATA	DETAILS
Type of Run	Whether the run was scheduled or triggered manually.
Date and Time	When the run, data and time, was initiated.
Outcome	Whether the run completed successfully or if it encountered errors.

You can click on the arrow icon next to the output to view run details such as an ingestion summary of objects ingested, download files (stored files), and additional timestamps



regarding the run.




FIELD DESCRIPTION Run Started The timestamp of when the run was initiated. Response The timestamp when the feed endpoint responded. Received **Data Ingested** The timestamp when the run was completed and intel data was ingested. **Query Range** The time frame for the data ingested. Zipped password-locked file(s) of the ingested data. Store Files A summary of ingested object types. Ingested Summary




Accessing an Intel Feed's Activity Log

The Activity for a feed will appear after the feed has performed an initial run.

1. Click on the **Settings 1** gear icon and select **My Integrations**.




The My Integrations page will load. All integrations currently installed on your platform, both enabled and disabled, can be found on this page. The Enabled tab will be selected by default.




2. Locate and click on the integration to load its details page.



The integration details page will load.



- 3. Select the **Activity Log** tab if not already selected.
- 4. Click on the arrow icon located next to a run's outcome status to view additional details regarding the run.





Job Management




The Job Management page is only accessible to users with Administrator or Maintenance accounts.

The Job Management page allows you to view the status and outcome of Bulk Actions.

To access the Job Management page:

1. Navigate to Settings > Job Management.



The Job Management page allows you to view the following details about a Bulk Action job:

FIELD	DESCRIPTION
Job ID	The unique ID assigned to the job.
Author	The user that initiated the job.
Action	The Bulk Action selected.
Search Criteria	The search filters used to select the system objects for the job.
Updates	The Bulk Action being performed on the system objects selected.



FIELD	DESCRIPTION
	Example: If you were to run a Bulk Action on a set of indicators to expire on 2-29-2020, the Updates field will display: indicator: {"expires_ats" : "2020-02-29"}
Status	The current status of the job. Possible statuses include: Created - The job has been queued. In-Progress - The job is running. Error - The job failed. Waiting - The job is waiting for indexing to be complete. This only applies to the Bulk Change process. Completed - The job has completed.
Completed	The timestamp of when the job completed.
Total	The total number of objects included in the job.
PID	The process ID of the worker executing the job.
Percent Completed	This represents the amount of system objects associated with the job that have been processed. Example: 100 indicators out of the 1000 associated with the job have been deleted = 10%.
Estimated Time Remaining	The estimated time remaining until the job is complete.
Date Created	The timestamp of when the job was created and queued.



FIELD	DESCRIPTION
Updated At	The timestamp of when the job or an system object associated with the job was last updated.
Start Time	The timestamp of when the job was started.
Completed At	The timestamp of when the job completed.
Failed At	If the job failed. the timestamp of when it failed.



Licensing

Your ThreatQ deployment requires a license to initialize the platform. ThreatQ Support provides the initial license and any subsequent licenses provided to maintain the platform. You apply the initial ThreatQ license during first boot, as described in the Installation. Any subsequent license updates can be applied in the ThreatQ user interface.

Access to additional ThreatQ products, such ThreatQ Investigations and ThreatQ Data Exchange, are tied to your ThreatQ platform license. Adding these features will result in ThreatQ Support issuing a new license to apply to your platform.



ThreatQ licenses are not perpetual.

Managing Your ThreatQ License

You can view and update your ThreatQ license using the ThreatQ user interface.

Viewing License Status

1. Click on the **Settings** icon and select **About**.

The License information window loads. You can also view additional licensing-based ThreatQ products, such as ThreatQ Investigations and ThreatQ Data Exchange (Publisher



Version 4.44.1-911

REGISTERED TO
jhasslin
PLATFORM
Expires 02/18/2021 (in 21 days)
INVESTIGATIONS
Expires 02/18/2021 (in 21 days)

Updating a License

If you receive a new license from Support, apply the new license by accessing the About page.

1. Click on the **Settings** icon and select **About**.

The License information window loads.

- 2. Select the **Update License** option.
- 3. Enter the new license key.
- 4. Click on Submit.



Navigation Menu

The table below outlines the ThreatQ navigation menu and its related processes.

THREA	TQ 🕽 🕍 Dashboards	III Threat Library A Investigations 🖧 Data Exchange 🖒 Integrations	+Create 7 Q A 3 P
#	NAME	DESCRIPTION	REFERENCES
1	ThreatQ lcon	Clicking on the ThreatQ icon will navigate you back to the home page and dashboard.	N/A
2	Dashboards	The Dashboards link in the top navigation bar allows you to access a drop-down list of your dashboards.	• Dashboards
3	Threat Library	Access and search the Threat Library and view system object details.	 Threat Library Building Searches with Filter Sets Object Details Bulk Actions Data Controls
4	Investigations	Navigates to ThreatQ Investigations, a cybersecurity situation room that enables collaborative threat analysis, investigation, and coordinated response.	• ThreatQ Investigations



#	NAME	DESCRIPTION	REFERENCES
5	Data Exchange	Allows the bi-directional sharing of threat intelligence across multiple ThreatQ instances.	Integrations Management
6	Integrations	Allows you to access the Marketplace as well as you integrations.	Integrations Management
7	Create Button	Create system objects.	AdversariesEventsFilesIndicatorsSignaturesSTIX
8	Search Icon	Perform a basic search for a system object.	 Building Searches with Filter Sets
9	Message Center Icon	Receive in-app notifications of system job processes such as Bulk Actions. Administrator and Maintenance account users will also receive feed health notifications.	• Notification Center



#	NAME	DESCRIPTION	REFERENCES
10	Help lcon	Click the Help icon to quickly access the Help Center, Product Updates, Getting Started Guides, and Video Demos. The search field at the top of the menu also gives you the option to search the Help Center.	Product UpdatesInstallationVideos
11	Site Settings	Allows you to manage your ThreatQ application settings as well as view your version and licenses.	 Exports Job Management Object Management Reports Server Administration System Configuration User Management Licensing
12	User Icon	Access your user profile.	• User Management



Notifications

The ThreatQ platform offers platform-related alerts in the form on in-app notifications, via the Notification Center, and feed health emails.

In-app notifications include Bulk Action updates and feed health alerts.



Only users with Administrator and Maintenance roles will receive in-app feed health alerts via the Notification Center.


Administrators and Maintenance account users can subscribe users to Feed Health Email Notifications . These users will receive an email when a feed encounters an error when preforming a run.



Feed Health Email Notifications

Feed Health Notifications allows the ThreatQ platform to send you, and other designated users, email notifications when a feed encounters an issue.

The emails, sent to users designated on the Notification Settings page, will contain useful information such as connection information, data ingested, and an ingestion summary.



Configuring Mail Server

You must enter your mail server information on the Mail Server Configuration tab before enabling Feed Health Notifications.




In the event that you have completed the mail server configuration and are still not receiving emails, your email provider may have marked the activity as suspicious. Some services, such as Gmail, will require you to confirm the activity, via an email message, before allowing the ThreatQ application to continue to use the server to send emails. A common symptom found in the error log is that you will receive an "incorrect password" error. If you are certain that the password you provided is correct, your mail service is likely blocking the service and requires your confirmation to proceed.



To Configure Mail Server:


1. Click on the **System Settings** gear icon and select the **Notification Settings** option.

The Notification Settings page loads.



2. Click on the Mail Server Configuration tab.

The Mail Server Configuration page loads.




3. Complete the following fields:



FIELD	DESCRIPTION
Server Name	The address of your mail server.
SSL Method	The SSL method used. There are three options: • SSL • TLS • None
Port #	The mail server port.
User name	The mail server account username.
Password	The mail server account password.



4. Enter an email in the **Test Email** field and click **Save and Send Test Email** to confirm that the settings are correct - this is optional. You will receive a setup confirmation email.



5. If you did not use the **Save and Send Test Email** option, click on **Save Changes** to save your settings.

Enabling Feed Health Notifications

There are two different types of Feed Health Notifications that can be enabled on this page: In-App and Email. While you can enter the email address for a user to receive Email Notifications, only users with administrator and maintenance roles will receive In-App Notifications.

If using Email Notifications, the Mail Server Configuration tab must completed before you enable the feature.




In the event that you have completed the mail server configuration and are still not receiving emails, your email provider may have marked the activity as suspicious. Some services, such as Gmail, will require you to confirm the activity, via an email message, before allowing the ThreatQ application to continue to use the server to send emails. A common symptom found in the error log is that you will receive an "incorrect password" error. If you are certain that the password you provided is correct, your mail service is likely blocking the service and requires your confirmation to proceed.

To Enable Feed Health Notifications:

1. Click on the **System Settings** gear icon and select the **Notification Settings** option.




The Notification Settings page loads.



- 2. Perform the following steps to enable email and in-app notifications:
 - > Enable In-App Feed Health Notifications
 - a. Click on the Enable toggle switch for In App Notifications.
 - > Enable Feed Health Email Notifications
 - a. Enter an email address in the account field and press the **<Enter>** or **<Return>** key.


Feed Health Notifications



b. Click on the **Enable** toggle switch for **Email Notifications**.



3. Use the toggle switch next to each feed to enable/disable notifications for individual feeds.






You can also enable/disable individual CDF feed notifications by clicking on the feed under Integrations and checking/unchecking the notifications checkbox.




Notification Center

The icon is located on the navigation menu for the platform. This allows you to monitor system processes while working within ThreatQ.

The Notification Center alerts you, via an in-app notification icon, when a platform process, such as a Bulk Action job, has been queued and/or completed.



Administrator and maintenance accounts can also receive feed health notifications via the Notification Center. See Enabling Feed Health Notifications section in the Feed Health Email Notifications topic.





Object Management

The Object Management section of the ThreatQ platform allows you work with:

SECTION	DETAILS
Indicator Statuses Management	Create and edit custom indicator statuses.
Indicator Types	View your platform's indicators types.
Event Types	Create and edit custom event types.



Indicator Statuses Management

The Indicator Statuses page allows you to view, duplicate, add, edit, and delete available system-wide indicator statuses. You cannot edit or delete indicator statuses provided by ThreatQ (Active, Expired, Indirect, Review, Whitelisted), but you can add, edit, and delete your custom statuses.

Indicator Status Assignment

Multiple factors affect the indicators created from the relations on an individual object in a request. When using API/Indicators/Consume, each individual object in the request JSON is an indicator, and each indicator can have additional indicator relations stored under an indicators field in that object. As a result, the status of an indicator depends on the configuration of the request JSON.

Indirect Indicator Status

When you set up a default status of Indirect, the system assigns this status to indicators in the following scenarios:

- A status or status_id field is not provided for the parent object.
- A status or status ID is not provided for the additional indicator relations of the object.
- The JSON request body includes duplicate indicators and one of the duplicates has a default status ID. If none of the duplicates has a default status ID, the system uses the status ID of the last duplicate.

Currently, the Indirect Indicator status only applies to IOCs related to a main indicator.

Protected Indicator Statuses

When doing insertions, ThreatQ determines if the indicator already exists and the Indicator status is a protected status, If so, the system retains the status.

Viewing Indicator Statuses



The Object Management page opens to the Indicator Statuses tab.

THREATQ

Let Deshboards

B. Threat Library

A Investigations

Indicator Statuses tab.

Object Management

Indicator Status

Poses a threat and is being exported to detection tools.

Associated to an active indicator or event (i.e. pDNS).

Poses NO risk and should never be deployed.

Requires further analysis.



□ Active

☐ Whitelisted

Statuses found within ThreatQ are listed by status, number, and description within the Indicator Statuses table.

0

0

0

2. Optionally, to sort the table by a column, click the column header. To reverse the column sorting order, click the header a second time.

Indicator Statuses Table Options:

FUNCTION	DESCRIPTION
Status Filter	Enter a keyword in the text field to filter the table by status name. You can click on the Statuses header to sort the table by alphabetical order.
Description Filter	Enter a keyword in the text field to filter the table by status description. You can click on the Description header to sort the table by alphabetical order.
Protect from Feed Override Clicking on the toggle switch in this column will enable/disable to Protect from Feed Override option for that status. See the Supplindicator Status Updates section below for more details on this	
Total Indicators	The number of indicators currently using the status. Clicking on the value will open the Threat Library filtered to that status. Clicking on the



FUNCTION

DESCRIPTION

Total Indicators heading will sort the table in ascending/descending order.

Suppressing Indicator Status Updates

Enabling the **Protect from Feed Override** option for a status, prevents feeds from automatically updating indicators with this status to another. Any status with a green toggle switch is currently protected from status updates. Those with grey toggle switches are not.



Use Case: You have a well-vetted set of whitelisted indicators that you do not want to update without internal review and discussion. To protect these indicators from automatic status updates from feeds, toggle the **Protect from Feed Override** switch for the **Whitelisted** status to green (active). After you make this change, ThreatQ retains the status of **Whitelisted** for any indicator to which it is assigned and suppresses any updated status information received from a feed.


1. Navigate to Settings ■ > Object Management.

The Object Management page opens to the Indicator Statuses tab.

2. In the Protect From Feed Override column, click the toggle switch corresponding to the status to change it from grey (status updates allowed) to green (status updates suppressed).


Adding an Indicator Status






2. Click Add New Status.

The Add a Status dialog box opens.




- 3. Enter a **Status Name**.
- 4. Optionally, enter a **Status Description**.
- 5. Click Add Status.

Editing an Indicator Status








2. Determine the indicator you want to edit and click **Edit** in the far right column.

The Edit Status dialog box opens.




- 3. Optionally, enter a new **Status Name**.
- 4. Optionally, enter a new **Status Description**.
- 5. Click Save Changes.

Deleting an Indicator Status



You cannot delete indicator statuses provided by ThreatQ. Custom statuses can only be deleted if there are no indicators using that status.





- 2. Determine the indicator you want to delete and select the corresponding checkbox in the first column.
- 3. Click the **Delete icon** in the upper right hand corner.

A confirmation dialog box appears.



4. Click Delete Statuses.




Indicator Types

The Indicator Types table allows you to view a list of indicator types found in ThreatQ and the total number of indicators associated with each type.

To view Indicator Types found within ThreatQ:

1. Navigate to Settings > Object Management.



2. Click the Indicator Types tab.




Event Types Table Functions:

FUNCTION	DESCRIPTION
Changing the number of entries displayed in the table	Click the dropdown menu at the top right of the table and select the desired option.
Filter table by Indicator Type	Enter a keyword in the text field provided to filter the table by indicator type.
Sort table by Total Indicators	Click the Total Indicators column header to sort the table by ascending/descending order.



Event Types

The Event Types page allows you to view, add, edit, and delete system events.





Event Types provided by ThreatQ cannot be edited or deleted, but you can add, edit, and delete your own custom event types.

System provided Event Types include:

- Anonymization
- · Command and Control
- Compromised PKI Certificate
- DoS Attack
- Exfiltration
- Host Characteristics
- Incident
- Login Compromise


- Malware
- Sighting
- Spearphish
- SQL Injection
- Attack
- Watchlist
- Watering Hole



Viewing Event Types


1. Navigate to Settings > Object Management.

The Object Management page opens.



2. Click the **Event Types** tab.

The Event Types tab opens.



Event Types Table Functions:




DESCRIPTION
Click the dropdown menu at the top right of the table and select the desired option.
Enter a keyword in the text field provided to filter the table by event type.
Click on Total Events column header to sort the table by ascending/descending order.
Click the Total Indicators column header to sort the table by ascending/descending order. Clicking on the value will open the Threat Library filtered to indicators linked to the event type as a related object. User-created Event Types will have an Edit link located to the right of the Total Indicator value. Clicking on the Edit link will open the Edit Event Type dialog box.

Adding an Event Type


1. From the main menu, select Settings ■ > Object Management.





2. Click the **Event Types** tab.


The Event Types tab opens.



3. Click Add New Event Type.



The Add Event Type dialog box opens.



- 4. Enter a Event Name.
- 5. Click **Add Type**.


Editing an Event Type

You can edit user-generated event types.



1. Navigate to Settings ■ > Object Management.


The Object Management page opens to the Indicator Statuses tab.



2. Click the **Event Types** tab.




The Event Types tab opens.



3. Determine the Event Type you want to edit and click **Edit** in the far right column.

The Edit Event Type dialog box opens.



- 4. Enter a new Event Name.
- 5. Click Save Changes.




Deleting an Event Type

A

You cannot delete an Event Type provided by ThreatQ. Custom Event Types can only be deleted if there are no events using that event type.

1. Navigate to Settings ■ > Object Management.


The Object Management page opens to the Indicator Statuses tab.



2. Click the **Event Types** tab.



The Event Types tab opens.



- 3. Determine the event type you want to delete and select the corresponding checkbox in the first column.
- 4. Click the **Delete icon** in the upper right hand corner.

A confirmation dialog box appears.



5. Click Delete Types.



Reports

You can export a PDF Summary of an object from an object's details page.

Generating Reports

Complete the following steps to export a PDF Summary of an object from an object's details page.

- 1. Access the object's detail's page for which you want to generate a report summary.
- 2. Select Actions > Generate PDF.

The PDF summary downloads and opens in a new browser tab.



Google Chrome Users: Google Chrome's pop-up blocker prevents object PDF summary reports from downloading. We recommend changing your browser settings to allow pop-ups from your ThreatQ instance. See Turning Off the Pop-up Blocker in Chrome for more information.



The generated PDF may contain active links to internal and external locations. Related objects in the PDF link to an internal ThreatQ instance that may require authentication. Please be aware of potential impacts before distribution of the generated report.

Turning Off the Pop-Up Blocker in Chrome

By default, Google Chrome blocks pop-ups from automatically showing up on your screen. When a pop-up is blocked, the address bar will display a pop-up blocked alert. This pop-up blocker will prevent your PDF from being downloaded. Complete the following steps to allow pop-ups from ThreatQ.

Procedure:

- 1. Go to ThreatQ where pop-ups are blocked.
- 2. In the address bar, click the **Pop-up blocked** alert icon.



- 3. Click the link for the pop-up you want to see.
- 4. To always see pop-ups for the site, select Always allow pop-ups from [your ThreatQ instance].
- 5. Click Done.

Report Options

You can navigate to **Settings > Report Options** to customize the PDF reports that are generated. Report options apply to all reports generated platform-wide. You can make the following customizations:

Customizing the Report Header

- 1. Select the **Settings** icon > **Report Options**.
- 2. Under **Header Banner**, complete one of the following steps:
 - Drag and drop the image you want to use as the header.
 - Click **Browse** and navigate to the image you want to use as the header.
- 3. Optionally, click Restore header banner to defaults.
- 4. Click Save.

Customizing Report Text Colors

- 1. Select the **Settings** icon > **Report Options**.
- 2. Under Colors, use the drop down menus to select:
 - Header Text
 - Heading Text
 - Body Text
- 3. Click Save.



Adding a Custom Disclaimer to a Report

You can add a custom disclaimer to include with your report to communicate any liabilities or limitations to the end users of the report.

- 1. Select the **Settings** icon > **Report Options**.
- 2. Under **Disclaimer**,enter your disclaimer text and then use the formatting tools to customize your message.
- 3. Click Save.

Previewing Report Customization

You can preview report customization to view a representation of a report's output.

- 1. Select the **Settings** icon > **Report Options**.
- 2. Under Customized PDF Reports, click Preview.

The sample report downloads to your computer.



Server Administration

The Server Administration dropdown link is only accessible to users with Administrative and Maintenance Accounts. Clicking on this option, found under the Settings, will open the **ThreatQ Monitoring Platform** in a new tab/window.

ThreatQ Monitoring Platform



The Server Administration dropdown link is only accessible to users with **Administrative** and **Maintenance** roles.

The ThreatQ Monitoring Platform provides a way for users with Administrative and Maintenance roles to monitor system resources and logs.

This feature is built upon Cockpit, a web-based interface that allows you to view the health of your server, system resources, as well as adjust configurations. You can access the full documentation on its operations at:

https://access.redhat.com/documentation/en-us/red_hat_enterprise_linux/7/html-single/getting started with cockpit/index#using cockpit

Creating a User Account for the ThreatQ Monitoring Platform

Since you cannot use a root user account to access the Server Administration console, you may need to use the Command Line Interface (CLI) to create a second non-root user account for access. Depending on your business processes, you may decide to assign ThreatQ user accounts to a specific group. However, you are not required to do so.

1. **Optional Step. You do not have to create a group for non-root users.** However, you can create one by entering the following command::





groupadd cockpit



- 2. Use one of the following methods to create a user:
 - Create a user as a part of a group:
 - <> adduser -G <groupname> <username>
 - adduser -G cockpit testUser
 - Create a user not assigned to a group:
 - <> adduser <username>
 - adduser testUser
- 3. Enter the following command to create a password for the user:
 - <> passwd <username>
 - passwd testUser

Changing password for user testUser.

New password:

Retype new password:

passwd: all authentication tokens updated successfully.

4. **Optional Step.** Enter the following command to create an admin user by adding the user account to the wheel group:

```
<> adduser -G wheel <username>
```

5. Use the new user account to log into the server administrator console.

Accessing the ThreatQ Monitoring Platform


A

Root user access is disabled for the ThreatQ Monitoring Platform.

1. Navigate to **Settings Server Administration**.



The ThreatQ Monitor Platform will load in a new tab/window.




2. Log into the platform using your user server credentials.



These credentials are not the same credentials that you use to log into the ThreatQ UI.

3. You will now be logged into the ThreatQ Monitoring Platform.







Sharing

ThreatQ's sharing functionality allows you to control access to Data Collections and Dashboards at the user level or give view-only access to all users. You can assign permissions when you create a data collection or dashboard and then update them at any time.

User Permission Levels

You can assign each user one of the following permission levels:

PERMISSION LEVEL

DESCRIPTION

Owner

By default, the user who creates a data collection or dashboard is designated as the owner. However, ownership can be reassigned by the owner at any time. If an owner selects a new owner, the original owner becomes an editor. In addition, if you delete an owner's user record, the system requires you to either reassign ownership to another user or delete the owner's data collections and dashboards.

Users with owner-level permission can:

- Reassign ownership.
- Change user and group permissions for the data collection or dashboard.
- Remove a user's permissions
- Modify or delete the data collection or dashboard.
- Change the name of the data collection or dashboard.

Editor

Editors have similar permissions to owners but cannot re-assign ownership of or delete the data collection or dashboard. In addition, they cannot change owner permissions or remove user permissions. Users with editor-level permissions can:

 Change user and group permission-levels for the shared data collection or dashboard.



•	Modify (/ the	data	collection	or	dashboard.
---	----------	-------	------	------------	----	------------

Viewer	Viewers can access the data collection or dashboard but cannot change it. In addition, they can view user permissions but cannot modify them.
Private	If you create a data collection and dashboard and do not assign permission to a user or group, only the owner can access it.

User Permission Levels and User Roles

You can assign any permission level to user accounts with the following user roles:

- Maintenance Account
- Administrative Access
- Primary Contributor Access

However, you can only assign viewer permission to a Read Only Access user account.



Ownership and public viewing permissions are applied to all data collections created before upgrading to version 4.54. Any data collections created by custom integrations (instead of Threat Library) are assigned ownership permissions for the custom integration client, but are not shareable. If you want to manage a data collection used by a custom integration in Threat Library in the future, you must first create it in Threat Library and then reference it in the custom integration.

View-Only Permissions for All Users

ThreatQ allows you to assign view-only permissions to all users. To do this, select a permission-level of **Everybody (Public)**. This assigns viewer permissions to all users unless they are assigned user-level permissions that are greater. For example, if I have editor permissions for the Adversary Hunt data collection and the other users have viewer permissions, when Bella (the owner) grants **Everybody (Public)** permissions, I retain my editor permissions. The viewers are now grouped together as **Everybody (Public)** and are no longer listed individually in the Sharing window's **Who has access** list.



Permission Conversion

When you upgrade to version 4.54, ThreatQ updates your existing permissions as follows:

- Data Collections For an existing data collection, the creator is automatically assigned owner permissions. All other users are assigned the group-level permission of Everybody (Public).
- Dashboards All users are assigned viewer permissions for ThreatQ's default dashboards and these permissions cannot be changed. All other user-created dashboards are assigned permissions based on the previous permission model.
 Dashboard creators have owner permissions. If a dashboard was shared with a user, the user retains the previously granted editor or viewer permissions.

Permission Levels and Integrations

User-managed integrations use data collections created and maintained in Threat Library. As such, user and group permission levels control access to these data collections.

Client-managed integrations are managed through the API. As such, user and group permissions do not control a client's ability to view, add, update or delete these data collections.

Legacy, Client-Managed Data Collections

For existing, client-managed data collections, the user who created it is assigned owner-level permissions. All other users are assigned view-only access through **Everybody (Public)** group permissions.

Client-Managed Integrations

Through the API, clients have full access to all data collections (view, add, update, and delete). As a result, the new permission levels (owner, editor, viewer) only apply when authenticating with username and password credentials (for example, as a user accessing the user interface) as opposed to authenticating with client credentials.

Legacy, User-Managed Data Collections

For each existing saved data collection, the user who created it has owner-level permissions. All other users have view access through the **Everybody (Public)** group permission.



System Configuration

The System Configuration section of the ThreatQ platform allows you:

SECTION	DETAILS				
Proxy	Enable and disable proxy settings.				
Account Security	Configure the number of failed login attempts before a user is locked out and the number of minutes a user will be locked out before being able to reattempt login.				
General Settings	Configure system date and time format as well as indicator parsing checkbox defaults.				



Proxy

The Proxy configuration page allows you to enable or disable proxies.



Users are required to set their proxy server settings to use http: for their https: traffic.


Accessing Proxy Configuration

1. Navigate to Settings ■ > System Configurations.

The System Configurations page opens to the Indicator Statuses tab.

2. Click the **Proxy** tab.

The Proxy Configuration tab loads.



Proxy Table Functions:

FUNCTION

DESCRIPTION

Enabling a proxy for HTTP or HTTPS traffic

1. Check the correct proxy type and enter configuration details. Click Save Changes. ThreatQ will check that the proxy has been configured properly.



FUNCTION DESCRIPTION

Disabling a proxy for HTTP or HTTPS traffic

1. Uncheck the proxy you wish to disable, and click Save Changes.



Account Security


The System Configuration: Account Security tab allows you to configure user lock out settings as well as the display of a custom login banner.

User Lockout Settings

The **Enhanced Security** section of the Account Security tab allows you to specify the number of failed login attempts before a user is locked out and the number of minutes a user will be locked out before he can attempt to log in again. By default, failed login attempts are set to five and the timeout period is set to thirty minutes.

Configuring User Lockout Settings

Navigate to Settings ■ > System Configurations.
 The System Configuration page loads with the Account Security tab selected by default.



3. Enter your changes to the following fields:

FUNCTION	DESCRIPTION			
Login Attempts	The number of consecutive failed login attempts before a user's account is temporarily locked.			



Account Timeout The number of minutes an account is locked after the specified number of failed log in attempts.

4. Click the Save button to save your changes.

Custom Login Banner

The Require Disclaimer Acceptance section of the Account Security tab allows system administrators to enable a custom message displayed to all users when logging into the ThreatQ Platform. When enabled, ThreatQ users are required to review and accept the message.



In order to comply with government regulations, a customer could configure a custom banner to display a message during login requiring users to accept additional privacy and security terms.

Banner Behavior

The **Require Disclaimer Acceptance** toggle allows you to enable/disable the display of the custom banner.

Require Disclaimer Acceptance



Once enabled, all users will be required to accept the disclaimer text provided below in order to log in to their account.

When the toggle is disabled:

- The banner title and body are visible to administrators in the **Account Security** tab, but the banner is not displayed to users upon log in.
- Users can access to the platform using only their credentials

When the toggle is enabled:

- After a user enters their login and password, the custom banner displays. Users must click the **Accept and Continue** button to access the platform.
- If a user closes the banner without clicking the **Accept and Continue** button, he is returned to the login screen and cannot access the platform until he clicks the Accept and Continue button.





Users are required to click the **Accept and Continue** button each time they log into platform.

• If a user is logged out and enters a URL for a specific page in the platform, the custom banner is displayed and he must click the **Accept and Continue** button to access the specified page.

Enabling a Custom Banner



Only administrators have access to enable the custom banner configuration fields in the **Account Security** tab on the *System Configuration* page.





System Configurations

Account Security

Proxy

General

Enhanced Security



Require Disclaimer Acceptance





Enabled

Once enabled, all users will be required to accept the disclaimer text provided below in order to log in to their account.

Disclaimer Title

Disclaimer Title



Save



- 2. Click the toggle switch in the Require Disclaimer Acceptance section to enable the display of the custom banner.
- 3. Enter the banner title to be displayed at the top of the banner in the Disclaimer Title field.
- 4. Enter the body of the message in the Description field.



The Description field supports standard text formatting as well as the use of links and tables.

5. Click the Save button.

The next time a user logs in, he is prompted to review and accept the custom banner before proceeding to the platform.



General Settings

You can configure default indicator parsing options and the date and time format of your choice system-wide within the ThreatQ platform from the **General** tab.



If you make changes to the date and time format while another user is working concurrently in the same ThreatQ installation, that user must refresh their browser for the changes to take effect.

Configuring Date and Time Format

- 1. Navigate to Settings > System Configurations.
- 2. Click the **General** tab.



The General tab opens.

System Configurations

Account Security

Date and Time

Date Format

- MM/DD/YYYY
- DD/MM/YYYY
- YYYY/MM/DD

Time Format

- 12 hour
- 24 hour

Indicator Parsing

Normalize URL Indicators

When checked, parsed URLs will have ports and leading protocol adjusted, as well as unneeded quotes and spaces removed. Learn more about URL normalization.

Parse for FQDNs

When checked, the Indicator Parser will parse FQDNs.

Product Analytics

Disabled Enabled



When enabled, ThreatQ will automatically collect product analytics data in order to enhance your user experience. For more information, reference our Privacy Policy.

- 3. Select the desired **Date Format**. Options include: MM/DD/YYYY, DD/MM/YYYY, YYYY/MM/ DD
- 4. Select the desired **Time Format**. Options include: 12 hour, 24 hours.
- 5. Click **Submit** to save your settings.

Configuring Indicator Parsing Presets

Users with Maintenance and Administrator roles can configure the default state of the Normalize URL Indicator and Parse for FQDNs checkboxes for the Parse for Indicators option of the Add Indicators dialog box.






Setting these default states does not lock the checkboxes. Users can select and deselect each option when parsing for an indicator in the Parse for Indicators dialog box.

- 1. Navigate to Settings 2 > System Configurations.
- 2. Click the **General** tab.

The General tabl loads.



3. Locate the Indicator Parsing heading and set the following options:

Normalize URL When checked, parsed URLs will have ports and leading protocol adjusted, as well as unneeded quotes and spaces removed.

DESCRIPTION

OPTION



Parse for FQDNs

When checked, the Indicator Parser will parse FQDNs from the text and derive FQDN indicators from URLs in the text.

Example (checked): URL: https://tqexample.com/table.jspa? query_string_example

Indicators created:

- tqexample.com/table.jspa (the URL)
- tqexample.com (the derived FQDN from the URL)

When unchecked, the Indicator Parser will not generate FQDN indicators from the parsed text.

Example (unchecked): URL: https://tqexample.com/table.jspa? query_string_example

Indicator created:

tqexample.com/table.jspa (the URL)

4. Click Save.

Opt In/ Opt Out of Product Analytics

The Product Analytics toggle allows you to disable/enable the sharing of analytics data with ThreatQuotient. Enabling analytics allows ThreatQuotient to collect anonymized data on user actions to improve the overall user experience.

1. Navigate to Settings ■ > System Configurations.



2. Click the **General** tab.

System Configurations

Account Security

Date and Time

Date Format

- MM/DD/YYYY
- DD/MM/YYYY
- YYYY/MM/DD

Time Format

- 12 hour
- 24 hour

Indicator Parsing

Normalize URL Indicators

When checked, parsed URLs will have ports and leading protocol adjusted, as well as unneeded quotes and spaces removed. Learn more about URL normalization.

Parse for FQDNs

When checked, the Indicator Parser will parse FQDNs.

Product Analytics

Disabled Enabled



When enabled, ThreatQ will automatically collect product analytics data in order to enhance your user experience. For more information, reference our Privacy Policy.

- 3. Locate the Product Analytics heading.
- 4. Click the toggle button to change the setting from Disabled to Enabled or vice versa.
- 5. Click Save.



System Objects

Threat data, both ingested and manually added, is referred to as System Objects and is sorted and categorized by object type.

System Objects include:

- Adversaries
- Attack Patterns
- Campaigns
- Courses of Action
- Events
- Exploit Targets
- Files
- Identities
- Indicators
- Intrusion Sets
- Malware
- Reports
- Signatures
- STIX
- Tasks



Adversaries


An Adversary is an individual or group that attempts to perform malicious actions against another individual or organization.

Use the steps below to create, edit and delete an Adversary.

Adding Adversaries

1. Go to **Create > Adversary**.

The Add an Adversary dialog box opens.



- 2. Enter a name.
- 3. Select a **Source** from the dropdown provided.



You can also click on Add a New Source if the desired source is not listed in the dropdown list . If administrators have enabled TLP view settings, users can select a TLP designation light for the new source in the dropdown list provided. See the Traffic Light Protocol (TLP) topic for more information on TLP schema.

Source

Demo
Select a source
Status

AMBER

GREEN
WHITE

NONE

- 4. Enter a description.
- 5. Select any **Related Objects** you need to link to the adversary. This field is optional.
- 6. Click Add Adversary.

Adding Context


See the Object Details section and its topics for details on adding context to an object such as adding sources, attributes, and related objects.

Editing Adversaries

1. Locate and click the adversary.

The Adversary Details page opens.





2. Click on **Edit** next to the Adversary name.

The Edit Adversary dialog box opens.




- 3. Make the desired change to the Adversary name.
- 4. Click on Save Adversary.

Deleting Adversaries

1. Locate and click on the adversary.

The Adversary Details page opens.





2. Click on the **Actions** menu and select **Delete Adversary**.

A confirmation dialog box appears.



3. Click on **Delete Adversary**.



Attack Patterns


An Attack Pattern is a description of a method used to exploit software.

Use the steps below to create, edit and delete an Attack Pattern.

Adding an Attack Patterns

1. Go to Create > Attack Pattern.


The Add Attack Pattern dialog box opens.



2. Enter a name.



- 3. Enter a description in the field provided.
- 4. Select a **Source** from the dropdown provided.



- 5. Select any **Related Objects** you need to link to the Attack Pattern. This field is optional.
- 6. Click Add Attack Pattern.

Adding Context


See the Object Details section and its topics for details on adding context to an object such as adding sources, attributes, and related objects.

Editing an Attack Pattern

1. Locate and click on the attack pattern.




The Attack Pattern's detail page opens.



2. Click on **Edit** next to the Attack Pattern's name.

The Edit Attack Pattern dialog box opens.




3. Make the desired change to the Attack Pattern name and click Save Attack Pattern.

Deleting an Attack Pattern

1. Locate and click on the Attack Pattern.



The Attack Pattern's details page opens.



2. Click on the **Actions** menu and select **Delete Attack Pattern**.

A confirmation dialog box appears.



3. Click on Delete Attack Pattern.



Campaigns

A Campaign is a group of behaviors that describe malicious activities taken against specific targets over a period of time.


Use the steps below to create, edit and delete a Campaign.

Adding a Campaign

1. Go to **Create > Campaign**.




The Add Campaign dialog box opens.



2. Enter a Name.



- 3. Enter a **Description** in the field provided.
- 4. Enter an Objective.
- 5. Select the **First Seen** and **Last Scene** times.
- 6. Select a **Source** from the dropdown provided.



- 7. Select any **Related Objects** you need to link to the Campaign. This field is optional.
- 8. Click Add Campaign.

Adding Context


See the Object Details section and its topics for details on adding context to an object such as adding sources, attributes, and related objects.

Editing a Campaign

1. Locate and click on the Campaign.




The Campaign's detail page opens.



2. Click on **Edit** next to the Campaign's name.

The Edit Campaign dialog box opens.




3. Make the desired change to the Campaign name and click **Save Campaign**.

Deleting a Campaign

1. Locate and click on the Campaign.



The Campaign's details page opens.



2. Click on the **Actions** menu and select **Delete Campaign**.

A confirmation dialog box appears.



3. Click on **Delete Campaign**.



Courses of Action


A Course of Action is a combination of risk response measures taken to address or prevent malicious attacks.

Use the steps below to create, edit and delete a Course of Action.

Adding a Course of Action

1. Go to **Create > Course of Action**.


The Add Course of Action dialog box opens.



2. Enter a Name.



- 3. Enter a **Description** in the field provided.
- 4. Select a **Source** from the dropdown provided.



- 5. Select any **Related Objects** you need to link to the Course of Action. This field is optional.
- 6. Click Add Course of Action.


Adding Context

See the Object Details section and its topics for details on adding context to an object such as adding sources, attributes, and related objects.

Editing a Course of Action

1. Locate and click on the Course of Action.


The Course of Action's detail page opens.





2. Click on **Edit** next to the Course of Action's name.

The Edit Course of Action dialog box opens.




3. Make the desired change to the Course of Action's name and click Save Course of Action.

Deleting a Course of Action

1. Locate and click on the Course of Action.


The Course of Action's details page opens.



2. Click on the **Actions** menu and select **Delete Course of Action**.



A confirmation dialog box appears.



3. Click on **Delete Course of Action**.



Events


Events are objects that focus on temporal incidents that have significant security impact.

Use the steps below to create, edit and delete an Event.

Adding Events

1. Go to Create > Event.

The Add Event dialog box opens.




- 2. Select the **Event Type**.
- 3. Select a **Source** from the dropdown list provided.



You can also click on **Add a New Source** if the desired source is not listed in the dropdown list . If administrators have enabled TLP view settings, users can select a TLP designation light for the new source in the dropdown list provided.





- 4. Add the date and time the event occurred in the **Date of Occurrence** fields.
- 5. Add an Event Title.
- 6. Select any **Related Objects** you need to link to the event. This field is optional.
- 7. Click Add Event.

Adding Context

See the Object Details section and its topics for details on adding context to an object such as adding sources, attributes, and related objects.


Editing Events

You can also update the Event Type by clicking on the **Type** dropdown located to the top-right of the Event's Object Details page.

1. Locate and click on the event.




The Event Details page opens.



2. Click on **Edit** next to the Event name.

The Edit Event dialog box opens.




- 3. Make the desired change to the Event Name and Event Date.
- 4. Click on Save Event.

Deleting Events

Locate and click the event.
 The Events Details page opens.




The Event Details page opens.






2. Click on the **Actions** menu and select **Delete Event**. Created: 04/17/2019 Event Date: 04/1



A confirmation dialog box appears.





3. Click on **Delete Event**.



Files

Files are received from various intelligence providers and may contain technical cybersecurity data such as indicators, adversaries, and malware samples.

Use the steps below to create, edit and delete a File.

Adding Files


1. Click **Create > File**.




2. Drag the file into the dialog box or browse and locate the file.



The Add a File Dialog box will update.



- 3. Update the **Title** if desired.
- 4. Select a **Source** from the dropdown list provided.



5. Select a **Category**.



6. Select whether to have the Malware Safety Lock on or off.



Enabling the safety lock will create a password-protected .zip file so any malware is safer for download. The system default password is "**infected**."

7. Add any desired tags.



Tags added will appear on the File's Details page.

- 8. Select any **Related Objects** you need to link to the file. This field is optional.
- 9. Click Save File.

Adding Context


See the Object Details section and its topics for details on adding context to an object such as adding sources, attributes, and related objects.

Editing Files


1. Locate and click on the file.



The File Details page opens.



Created: 03/12/2019 First Seen: 03/12/2019 07:27am



2. Click on **Edit** next to the File name.

The Edit File dialog box opens.




- 3. Make the desired change to the File Name.
- 4. Click on Save File.




Deleting Files

1. Locate and click on the file.






2. Click on Actions menu and select Delete File.



A confirmation dialog box appears.



3. Click on Delete File.



Identities

An Identity contains basic identifying information for targeted groups such as information sources, threat actor identities, and targets of attack.


Use the steps below to create, edit and delete an Identity.

Adding an Identity

1. Go to **Create > Identity**.




The Add Identity dialog box opens.



- 2. Enter a Name.
- 3. Enter a **Description** in the field provided.
- 4. Enter the **Contact Information** in field provided.
- 5. Select a **Source** from the dropdown provided.





- 6. Select any **Related Objects** you need to link to the Identity. This field is optional.
- 7. Click **Add Identity**.


Adding Context

See the Object Details section and its topics for details on adding context to an object such as adding sources, attributes, and related objects.

Editing an Identity

1. Locate and click on the Identity.


The Identity's detail page opens.



2. Click on **Edit** next to the Identity's name.



The Edit Identity dialog box opens.




3. Make the desired change to the Identity's name and click Save Identity.

Deleting an Identity

1. Locate and click on the Identity.

The Identity's details page opens.



2. Click on the **Actions** menu and select **Delete Identity**.



A confirmation dialog box appears.



3. Click on **Delete Identity**.



Incidents

An Incident is a record of any violation of an organization's established security/network policy that may compromise security, integrity, or general access.


Use the steps below to create, edit and delete an Incident.

Adding an Incident

1. Go to **Create > Incident**.



The Add Incident dialog box opens.




- 2. Enter a Name.
- 3. Enter a **Description** in the field provided.
- 4. Select the **First Seen** and **Last Scene** times.
- 5. Select a **Source** from the dropdown provided.



You can also click on **Add a New Source** if the desired source is not listed in the dropdown list . If administrators have enabled TLP view settings, users can select a TLP designation light for the new source in the dropdown list provided.





- 6. Select any **Related Objects** you need to link to the Incident. This field is optional.
- 7. Click Add Incident.

Adding Context

See the Object Details section and its topics for details on adding context to an object such as adding sources, attributes, and related objects.

Editing an Incident

1. Locate and click on the Incident.


The Incident's detail page opens.



2. Click on **Edit** next to the Incident's name.



The Edit Incident dialog box opens.




3. Make the desired change to the Incident's name and click Save Incident.

Deleting an Incident


1. Locate and click on the Incident.

The Incident's details page opens.



2. Click on the **Actions** menu and select **Delete Incident**.

A confirmation dialog box appears.





3. Click on **Delete Incident**.



Indicators

An Indicator is information that describes or identifies methods used to defeat security controls, exploit vulnerabilities, and gain unauthorized access to an internal network. Indicators can also describe malicious reconnaissance to gather technical information, malicious cyber command and control, and any other attribute of cyber security whose disclosure is prohibited by law.

Indicators can be scored to allow you to apply weighting using contextual information, such as sources, attributes, and indicator types, as they are added to ThreatQ. You can also set a manual score per indicator.

You can also apply expiration dates to an indicator to when it is determined to pose less of a threat to your infrastructure than other indicators.

Adding an Indicator

1. Click on Create > Indicator.

The Add Indicators dialog box opens.

Add Indicators

Parse For Indicators

Add Indicator

Value

Type

Source

Add new source

Status

Related Objects (optional)

Llimit search to
All Objects

Add Indicator



- 2. Enter a value in the **Value** field.
- 3. Select the **Type** of Indicator.
- 4. Select a **Source** from the provided dropdown list. You can also click on **Add a New Source** if the desired source is not listed in the dropdown list. If administrators have enabled TLP view settings, users can select a TLP designation light for the new source in the dropdown list provided. See the Traffic Light Protocol (TLP) topic for more information on TLP schema.



- 5. Select a **Status** for the indicator.
- 6. Select any **Related Objects** you need to link to the indicator. This field is optional.
- 7. Click Add Indicator.

Adding Context


See the section and its topics for details on adding context to an object such as adding sources, attributes, and related objects.

Editing Indicators

1. Locate and click on the indicator.



The Indicator Details page opens.




Created: 04/17/2019 First Seen: 04/12/2019 07:49pi



2. Click on **Edit** next to the Indicator name.

The Edit Indicator dialog box opens.




- 3. Make the desired change to the indicator **Value** and **Type**.
- 4. Click on Save Indicator.

Deleting an Indicator

1. Locate and click on the Indicator.



The Indicator Details page opens.



2. Click on **Delete this Indicator** located to the top right of the page.

A confirmation dialog box appears.



3. Click on Delete Indicator.



Parsing for an Indicator




See the Importing Indicators via CSV topic for specific instructions and examples on parsing indicators from a .csv file.

1. Click on the **Create** button, located at the top of the dashboard and select **Indicator Parser** under the *Import* heading.



You can also click on **Create** > **Indicator** and then select the **Parse for Indicators** option at the top of the **Add Indicators** dialog box.

The Add Indicators dialog box will load.



- 2. Do one of the following:
 - Drag your file(s) into the left pane.
 - Click on Click to Browse, and locate the file you wish to upload.
 - Copy/paste the content in the right pane.



- 3. Select the Parser.
- 4. Review and update, if needed, the parsing checkbox options.

Parsing options include:

OPTION DESCRIPTION Normalize URL When checked, parsed URLs will have ports and leading protocol Indicators adjusted, as well as unneeded quotes and spaces removed. See the Indicator URL Normalization topic for more details. Parse FQDNs When checked, the Indicator Parser will parse FQDNs from the text and derive FQDN indicators from URLs in the text. **Example (checked)**: URL: https://tgexample.com/table.jspa? query_string_example Indicators created: tqexample.com/table.jspa (the URL) tqexample.com (the derived FQDN from the URL) When unchecked, the Indicator Parser will not generate FQDN indicators from the parsed text. **Example (unchecked)**: URL: https://tqexample.com/table.jspa? query_string_example Indicator created: tqexample.com/table.jspa (the URL)




Administrators can configure the default setting for these options under the General Tab on the System Configurations page. See the Indicator Parsing Presets topic for more details.

5. Click Next Step.



The Step 1 Import page will load.





If at any point, you wish to abandon the import, click Abandon this import.

6. Select whether to save or delete the file after the import.



Steps 7-9 pertain to saving the file. Skip to step 10 if you are not saving the file after import or did not upload a file on the previous step.

- 7. Update the **File Title** if needed.
- 8. Enter an optional File Description.
- 9. Confirm or update the File Category.
- 10. Select a **Source** from the dropdown menu provided.



You can also click on Add a New Source if the desired source is not listed in the dropdown list . If administrators have enabled TLP view settings, users can select a TLP designation light for the new source in the dropdown list provided. See the Traffic Light Protocol (TLP) topic for more information on TLP schema.

Source

Demo
Select a source
Status


AMBER

GREEN
WHITE
NONE

- 11. Select a **Status** to be applied to the extracted indicators.
- 12. Enter any Tags that should be applied to the extracted indicators.
- 13. Select any optional **Attributes** to be applied.
- 14. Add Relationships for the imported indicators.
 - If you enter an object name that is not found, you can click the **Create** link to add the new object. If you limit your search to a specific object type, you are linked to the corresponding form. For example, if you limit your search to Adversaries, the **Create** link opens the Add An Adversary form. If you leave the Limit search to field set to All Objects, you can select the object type you want to create from a drop-down list.

15. Click Next Step.

The Step 2: Organize and Classify page will load.



- 16. Locate and select one or more indicators using one of the following options:
 - Original Content (on the left)



- From the table (on the right)
- By using the Select dropdown menu
- The Value, Type, Status, and Source sortable headers.
- 17. Once you have selected one or more indicators, you can perform these functions via the **Add Info** link:


FUNCTION	DETAILS
----------	---------

TONCHON	DETAILS
Add Attributes	Add one or more attributes to the selected indicators.
Set Status	Set a status for the selected indicators.
Create Relationship	Link the selected indicator(s) to another object. When you add a relationship, it is displayed in the indicator list and you can click it to view details in a preview panel.
	If the object you want to link is not found, you can you can click the Create link to add the new object. If you limited your search to a specific object type, you are linked to the corresponding form. For example, if you limited your search to Adversaries, the Create link opens the Add An

click the **Create** link to add the new object. If you limited your search to a specific object type, you are linked to the corresponding form. For example, if you limited your search to Adversaries, the **Create** link opens the Add An Adversary form. If you leave the **Limit search to** field set to All Objects, you can select the object type you want to create from a drop-down list. In the Add form, the indicators you selected in the second step of the import process are listed in the Create Relationship section.

Add Comment Add a comment to the selected indicators.





18. You can edit the value or type of an indicator by clicking the pencil icon located to the left of the value.



You can also update the **Status** and **Type** of an indicator listed in the table by clicking the existing value in the row to reveal a dropdown. Use the dropdown to select a new Status or Type.





19. **Add Indicator** - If you notice an indicator on the left that was not extracted, you can add it by clicking Add Indicator and completing the process.



20. Click on Finish Import.



Indicator Expiration

Expiration ("Expired") is a status that can be assigned to an indicator. The expired status should be used when an indicator is deemed by an analyst to pose less of a threat to their infrastructure than other indicators.

Ways an Indicator can Expire

An analyst manually changes an indicator(s) status to "Expired"

This can be achieved by visiting an individual indicator's details page, then using the Status dropdown in the top right hand corner of the page to change the status.

If the analyst wishes to change the status of multiple indicators at the same time, they can use the advanced search tool to find the indicators they'd like to update, then click the Bulk Update button found directly to the right above the search results.

An analyst manually sets an expiration date for a specific indicator

Each indicator has the option to have an expiration date set, which once past, will toggle the status of that indicator from it's current status to "Expired".


• An expiration policy has been applied to the source reporting an indicator and therefore an expiration date is automatically set for that indicator during ingestion

Using the "Expiration" tab on the Indicator Management page, a ThreatQ admin has the ability to apply expiration policies to all ingested information, both new and existing, coming from a specific intelligence source. See the Indicator Expiration topic for more details.



Changing the Expiration Date for an Individual Indicator

When viewing a specific indicator, its expiration date can be changed by clicking on the link next to the expiration information.



Options include:

OPTION	DESCRIPTION
Add 7 Days	This will extend the current expiration date by 7 days.
Add 14 Days	This will extend the current expiration date by 14 days.
Protect from Auto- Expiration	This will set the indicator to "Never Expire". Once set, this indicator will be exempt from all automated expiration processes regardless of circumstances. The only way for this indicator to expire moving forward is by analyst choice.
Remove Current Expiration Date	This will remove the currently set expiration date. If this indicator is reported by an intelligence feed (with an expiration policy) in the future, a new expiration date will be added at that point in time.



Changing the Expiration Date for Multiple Indicators

You can apply expiration changes for a set of indicators using the Bulk Action function. See the Bulk Actions topic for further details.



Indicator Scoring

Indicator scoring allows you to apply weighting to indicators and their contextual information, such as sources, attributes, and indicator types, as they are added to ThreatQ. Indicator scoring allows you to set manual scores or you can rely on ThreatQ's scoring algorithm to calculate scores. After scores are calculated, you can change the score as desired to your custom value or accept the calculated value.

Building a Scoring Algorithm

You can build a scoring algorithm that will automatically assign an indicator score based on user-designed criteria. See the Scoring Algorithms topic for further details.


Setting a Manual Indicator Score




You can use this process to override an individual indicators score set by the scoring algorithm.

1. Navigate to an Indicator's Details page.

2. Click the **Score** dropdown and select a score.









Indicator Status

Every indicator in the system will have a status applied to it.



Most exports in ThreatQ are configured to use the **Active** status to signal deployment to external devices. However this can be modified and each status can be used however your organization sees fit.

DECCRIPTION

Default Statuses

CTATLIC

The default statuses that ship with a standard installation of ThreatQ are as follows:

STATUS	DESCRIPTION
Active	Poses a threat and is being exported to detection tools.
Indirect	Associated to an active indicator or event (i.e. pDNS).
Review	Requires further analysis.
Whitelisted	Poses NO risk and should never be deployed.
Expired	Indicator has reached its expiration and has been is deemed by an analyst to pose less of a threat to their infrastructure than other indicators.




Custom Statuses

You can create custom statuses for use in your ThreatQ instance. See the Indicator Statuses topic for more details.

Changing the Status of an Individual Indicator

Changing an indicator's status is straightforward, except in the case of whitelisting CIDR Block indicators. When whitelisting a CIDR Block indicator, this process generates a whitelisting rule. See the Whitelisted Indicators topic for more information.

- 1. Locate and click the indicator to open its details page.
- 2. Click the status dropdown menu, and select the desired status.



The status will be updated.



If an Administrator or the Primary Contributor are whitelisting a CIDR BLOCK indicator, there is a different process, as this actually generates a whitelisting



rule. For more information, see the Creating a Whitelist Rule section of the Whitelisted Indicators topic.

Changing the Status for Multiple Indicators

You can change the status for multiple indicators using the Bulk Status Change. See the Bulk Actions topic for more information.



Indicator URL Normalization

Remove Quotes from the Beginning and/or End of an Indicator

Single and double quote characters are removed if they are the first or last character of an indicator.

Remove Unneeded Spaces found within an Indicator

All spaces irrelevant of their position in the Indicator value are removed (when applicable).

Adjust leading protocol from indicators

Indicators with a leading protocol [http://, https://, ftp://, or ftps://] are extracted and included as an attribute. When applicable, this indicator adjustment could change the indicator type from URL to FQDN.



Original URL indicator of http://evilsubdomain.no-ip.biz/ would convert to a FQDN = evildomain.no-ip.biz.

Adjust the Port from an IP Address

An IP address with a port [ex. 199.7.136.88:8143] will be truncated to the IP address and the port assignment will be added as an attribute.

Using the previous example the following indicator/attribute will be created:

FIELD	VALUE
URL	199.7.136.88
Attribute > Port	8143

Adjust Defanged/Neutered Indicators

Indicators that have been defanged/neutered in order to "safely" share them (i.e. www [dot] 3322 [dot] org or badguy [at] gmail.com) need to be adjusted during import in order to ensure the indicators are properly deployed.



Create an IP Address from a URL (when applicable)

Using the previous example the following indicators will be created:

FIELD	VALUE
URL	51.255.131.66/civis/viewforum.php
IP Address	51.255.131.66

Create a FQDN from a URL (when applicable)

When a URL contains a domain [ex. bat99-11611.co/gate777.php] a second indicator will be created for the domain [bat99-11611.co].

Using the previous example, the following indicators will be created:

FIELD	VALUE
URL	bat99-11611.co/gate777.php
FQDN	bat99-11611.co

Extract HTTP Parameters from a URL Indicator

HTTP parameters [chained.j3oilgasinc.net/civis/viewforum.php? keywords=9obo&fid0=c27] are important but can significantly limit pattern-matching detection capabilities due to the likelihood of parameter deviations, as well as, hamper the volume of URL indicators being deployed. To increase the probability of detection the http parameters are extracted and created as attributes.

In this example:

FIELD		VALUE
URL IOC		chained.j3oilgasinc.net/civis/viewforum.php



Attribute = HTTP Parameter = keywords 9obo&fid0=c27

Maintain "WWW" on FQDN Indicators

When parsing or importing a FQDN the "www" will be maintained.

Replace and/or Remove Special Characters

CHARACTER	REPLACEMENT
ASCII Values < 32 ASCII Values > 127	<space></space>
Ascii 96	-
Ascii145	r
Ascii146	r
Ascii147	п
Ascii148	п
Ascii151	-
carriage return and line feed	<space></space>
Control Characters	Remove
Convert to UTF8	Remove leading and trailing space, tab, newline, carriage return, vertical tabs and null characters.



Importing Indicators via CSV

You can parse a .csv file for indicators using the ThreatQ CSV File Parser.



A .csv example file is available for download to serve a reference as you build your own .csv.

Download CSV Example

CSV Files with 1000+ Rows

- Attempt to break the file into smaller parts and import.
- If you cannot break down the file, contact ThreatQ Customer Success about implementing a dedicated parser using the Configuration Driven Feed (CDF) framework.

CSV Columns

The column headers marked with an * in the table below are required for the CSV file. Failure to include these required columns will result in the import process failing. All other column headers are optional and will not cause the import process to fail if not included.



Object and Attribute Sources cannot be added through the CSV file itself. A source value is added in the Step 7 of the import process, listed below, and is selected by the user.



The ThreatQ parser is case sensitive. When creating your CSV file, confirm that you are using the correct spelling and case for column headers as listed below.


COLUMN	DETAILS
HEADER	DETAILS

This field identifies the indicator name/value. *Indicator

> ThreatQ requires that the Indicator column be included in the csv file and that each entry have a value.



Example



*Type


This field identifies the indicator type.

ThreatQ requires that the Type column be included in the csv file and that each entry have a value.



You must use a type that already exists in your ThreatQ instance. If you are unable to provide an Indicator Type for each indicator, you can use the **Generic Text/PDF** parsing option that will attempt to ID indicator type values automatically.

Example



*Status


The Status column is required. You may leave the values blank as you will have the option to select a status to use during the import process. If you decide to enter values in the CSV, you must use a status that already exists in your ThreatQ instance. You can review your existing status by clicking on the **Settings** gear icon and selecting **Object Management**.



The status supplied in the CSV will be used over the status selected during the import process. Any blank fields will use the status selected during the import process.



Example



Attribute

The Attribute columns are optional. You can apply one or more attributes to an indicator by adding an Attribute column.

Attribute keys are **case** and **space** sensitive, 'MalwareFamily' and 'malware family' will generate a separate key in ThreatQ. In order to map to an existing Attribute Key in ThreatQ, you must match exactly.

Each attribute column heading must use the follow format:

Attribute::<Attribute Name>



It is recommended to review existing attribute keys and values in ThreatQ prior to importing so that you can maintain consistent and normalized attribute data.

Example




Comments

The optional Comments allows you to add a comment to include with the indicator.

The ThreatQ user that performs the import process will be marked as the author of the comment in ThreatQ.






Parsing a Threatq CSV File and Adding Context

1. Click the **Create** button and select **Indicator Parser** under the *Import* heading.

The Add Indicators dialog box will open with the Parse for Indicators tab selected.





- 2. Upload your CSV file by either:
 - Dragging and dropping your file into the window
 - · Clicking on the Click to Browse option and uploading your file
- 3. Select **ThreatQ CSV File** as the parser to use.
- 4. Use the checkboxes to select your parsing options:

OPTION

DESCRIPTION

Normalize URL Indicators

When checked, parsed URLs will have ports and leading protocol adjusted, as well as unneeded quotes and spaces removed.



Normalization also adds attributes for protocol and query string.

See the Indicator URL Normalization topic for more details.

Parse FQDNs

When checked, the Indicator Parser will parse FQDNs from the text and derive FQDN indicators from URLs in the text.

Example (checked): URL: https://tqexample.com/table.jspa? query_string_example

Indicators created:

- tqexample.com/table.jspa (the URL)
- tqexample.com (the derived FQDN from the URL)

When unchecked, the Indicator Parser will not generate FQDN indicators from the parsed text.

Example (unchecked): URL: https://tqexample.com/table.jspa? query_string_example

Indicator created:


tqexample.com/table.jspa (the URL)






Administrators can configure the default setting for these options under the General Tab on the System Configurations page. See the Indicator Parsing Presets topic for more details.

- 5. Click Next Step.
- 6. Select whether or not to save the CSV file. Saving the file will result in all extracted indicators being linked to the file for reference.



7. Select a **Source** for the extracted indicators.





8. Select a **Status** for the extracted indicators. If you supplied a status in the CSV file, that value will be applied to the indicators. Any entries in the CSV without a status value will be assigned the status you select in this step.



- 9. Enter any **Tags** to apply to the extracted indicators. This field is optional.
- 10. Select any attribute, attribute value, and attribute source to apply to the extracted indicators.
- 11. Add **Relationships** for the extracted indicators.



If you enter an object name that is not found, you can click the **Create** link to add the new object. If you limited your search to a specific object type, you are linked to the corresponding form. For example, if you limit your search to Adversaries, the **Create** link opens the Add An Adversary form. If you leave the **Limit search to** field set to All Objects, you can select the object type you want to create from a drop-down list.

12. Click on **Next Step**.

The Step 2: Organize and Classify page will load.



13. You can review the extracted indicators' information and attributes.

You can perform the following actions:

ACTION DETAILS

Add Indicator

You can add additional indicators by clicking on the Add Indicator button.



Edit Indicator Type and Value

You can edit the Indicator Type by clicking on the Pencil icon next to the indicator name. The Edit Indicator screen will load. You can edit the extracted indicator's value and type from this box.

Set/Update Status

You can update the status of one or more extracted indicators. Select the checkbox next to the indicator(s) to update and then click on the **Add Info** option. Click on the **Set Status** tab and select your new status.

Add Attribute

You can add an attribute to one or more extracted indicators. Select the checkbox next to the indicator(s) to update and then click on the **Add Info** option. The Add Attributes tab will be selected by default. Select an **Attribute Name**, **Value**, and **Source** to apply to the selected indicator(s).

Create Relationship

You can link one or more extracted indicators to another system object. Select the checkbox next to the indicator(s) to update and then click on the **Add Info** option. Click on the **Set Relationship** tab and set the relationship. When you add a relationship, it is displayed in the indicator list and you can click it to view its details in a preview panel.



If the object you want to link is not found, you can you can click the **Create** link to add the new object. If you limited your search to a specific object type, you are linked to the corresponding form. For example, if you limited your search to Adversaries, the **Create** link opens the Add An Adversary form. If you leave the **Limit search** to field set to All Objects, you can select the object type you want to create from a drop-down list. In the Add form, the indicators you selected in the second step of the import process are listed in the Create Relationship section.

Add Comment

You can add a comment to one or more extracted indicators. Select the checkbox next to the indicator(s) to update and then click on the **Add Info** option. Click on the **Set Comment** tab and enter your comment.



Delete
Extracted
Indicator

You can delete one or more extracted indicators. Select the checkbox next to the indicator(s) to delete and then click on the **Remove** icon.

14. Click Finish Export.

Troubleshooting

If the CSV fails to parse please review the following points:

- Verify that the file is a CSV.
- Verify that column headers are spelled exactly as they are listed, the parser is case sensitive.
- Verify that all rows have a value for Indicator and Type.
- Verify that all Type and Status values are valid and exist in ThreatQ.



If you have previously hit a failed parse run and believe you have fixed the error but the file will still not parse, logout of TQ, log back in and attempt to parse again.



Supported Defanging Techniques

The table below lists all supported indicator defanging techniques.

[.]	=>	
L•J		•

(dot) => .

[d] => .

-dot- => .

dot => .

hxxp:// => http://

hxxx:// => http://

hxxps:// => https://

hxxxs:// => https://

[hxxp] => http

hxtp:// => http://

htxp:// => http://

hxtps:// => https://

htxps:// => https://



[http]	=>	http
[http://]	=>	http://

[www] => www



Intrusion Sets


An Intrusion Set is a grouped set of adversarial behaviors and resources, sometimes referred to as attack packages, used to target an individual organization.

Adding an Intrusion Set

1. Go to Create > Intrusion Set.

The Add Intrusion Set dialog box opens.






- 2. Enter a Name.
- 3. Enter a **Description** in the field provided.
- 4. Select the **First Seen** and **Last Scene** times.
- 5. Select a **Source** from the dropdown provided.



You can also click on **Add a New Source** if the desired source is not listed in the dropdown list . If administrators have enabled TLP view settings, users can select a TLP designation light for the new source in the dropdown list provided.





- 6. Select any **Related Objects** you need to link to the Intrusion Set. This field is optional.
- 7. Click Add Intrusion Set.


Adding Context

See the section and its topics for details on adding context to an object such as adding sources, attributes, and related objects.

Editing an Intrusion Set

1. Locate and click on the Intrusion Set.


The Intrusion Set's detail page opens.



2. Click on **Edit** next to the Intrusion Set's name.



The Edit Intrusion Set dialog box opens.




3. Make the desired change to the Intrusion Set's name and click Save Intrusion Set.

Deleting an Intrusion Set

1. Locate and click on the Intrusion Set.

The Intrusion Set's details page opens.



2. Click on the **Actions** menu and select **Delete Intrusion Set**.



A confirmation dialog box appears.



3. Click on **Delete Intrusion Set**.



Malware


Malware, short for malicious software, targets devices, services, and networks with the intent to gain unauthorized access or damage a network or programmable device.

Use the steps below to create, edit and delete a Malware object.

Adding a Malware Object


1. Go to **Create > Malware**.

The Add Malware dialog box opens.





- 2. Enter a name.
- 3. Enter a description in the field provided.
- 4. Select a **Source** from the dropdown provided.



- 5. Select any **Related Objects** you need to link to the Malware. This field is optional.
- 6. Click Add Malware.

Adding Context


See the section and its topics for details on adding context to an object such as adding sources, attributes, and related objects.

Editing a Malware Object

1. Locate and click on the Malware.




The Malware's detail page opens.



2. Click on **Edit** next to the Malware's name.

The Edit Malware dialog box opens.




3. Make the desired change to the Malware name and click **Save Malware**.

Deleting a Malware Object

1. Locate and click on the Malware.



The Malware's details page opens.



2. Click on the Actions menu and select Delete Malware.

A confirmation dialog box appears.



3. Click on Delete Malware.



Reports


A Report contains information and related details for a specific threat such as Reports and malware.

Use the steps below to create, edit and delete a Report.

Adding an Reports


1. Go to **Create > Report**.

The Add Report dialog box opens.





- 2. Enter a name.
- 3. Enter a description in the field provided.
- 4. Select a **Source** from the dropdown provided.



- 5. Select any **Related Objects** you need to link to the Report. This field is optional.
- 6. Click Add Report.

Adding Context


See the section and its topics for details on adding context to an object such as adding sources, attributes, and related objects.

Editing an Report

1. Locate and click on the Report.




The Report's detail page opens.



2. Click on **Edit** next to the Report's name.

The Edit Report dialog box opens.




3. Make the desired change to the Report name and click **Save Report**.

Deleting an Report

1. Locate and click on the Report.



The Report's details page opens.



2. Click on the **Actions** menu and select **Delete Report**.

A confirmation dialog box appears.



3. Click on **Delete Report**.



Signatures

A Signature contains the "blueprints" or pattern associated with a malicious attack on a network or system.

ThreatQ provides you with the ability to ingest and manage Signatures, such as Snort, YARA, and OpenIOC. While importing, ThreatQ parses the signature file for Indicators to add. Once signatures are included in your deployment, you can add contextual information and correlate them with Indicators, Events, Adversaries, and Files.

Adding a Signature

1. From the main menu, choose **Create > Signature**.

The Add Signatures

Abandon this import

What type?

Source

Add Amazonce

Provide the content you'd like to be parsed for signatures.

CopylPaste content here...

Orag your files here or click to browse

Supported file types include: Jules. Jules

- 2. Choose the type of signature from the dropdown .
- 3. Select a **Source** from the dropdown provided.



ď

You can also click on **Add a New Source** if the desired source is not listed in the dropdown list. If administrators have enabled TLP view settings, users can select a TLP designation light for the new source in the dropdown list provided. See the Traffic Light Protocol (TLP) topic for more information on TLP schema.



- 4. Do one of the following:
 - Drag your file(s) into the left pane.
 - Click click to browse, and locate the file you wish to upload.
 - Copy/paste content into the right pane.
- 5. Optionally, select to parse the signature for indicators.
- 6. Choose a **Signature Status** from the drop-down menu.
- 7. Optionally, Apply attributes to all extracted signatures:
 - Select an Attribute Type.
 - Enter an Attribute Value.
 - Enter an Attribute Source.



You can click on the **Add** icon for additional attributes.

- 8. Optionally, relate the signature to another object by entering the object in the **Relate** signatures to another object field.
- 9. Click Next Step.




If signatures are discovered, the Results dialog box appears.



10. You can either select **Submit Import** to finish adding the signatures or **Review** to customize what data is imported.


If you selected to review signatures, the Add Signatures Step 2: Review page loads.



- 11. Select one or more signatures and click **Delete**.
- 12. Click on **Show Details** for a signature to review individual items in a signature. Use the checkboxes to select unwanted signature items and click **Delete**.



A warning dialog box appears.



- 13. Click **Delete** to remove the unwanted items.
- 14. Click **Create Signatures** when finished.



STIX



ThreatQ supports STIX 1.1.1, STIX 1.2 and STIX 2.0.

ThreatQ allows you to ingest and manage STIX files. You can ingest STIX data in two ways:

- You can set up a STIX/TAXII Feed.
- You can upload a STIX file or insert STIX data to parse for indicators.

ThreatQ STIX Object Types

STIX integration provides ThreatQ with the following additional object types.

- Campaigns
- Courses of Action
- Exploit Targets
- Incidents
- TTP objects
- Identities (STIX 2.0)
- Reports (STIX 2.0)
- Vulnerabilities (STIX 2.0)

These objects enable better understanding and communication of STIX data. STIX data will be mapped to these objects and existing objects in the system.

Parsing a STIX File for Indicators

ThreatQ allows you to upload a STIX file or insert STIX data to parse for indicators.

- 1. Click the **Create** button, located at the top of the dashboard and select **STIX Parser** under the *Import* heading.
 - The Parse for Intelligence window is displayed.
- 2. Do one of the following:
 - Drag your file(s) into the left pane.



- Click on Click to Browse, and locate the file you wish to upload.
- Copy/paste the content in the right pane.
- 3. The **Normalize URL Indicators** check box defaults to checked. You can click the check box to unselect it or leave it checked. See <u>Indicator URL Normalization</u> for more information.
- 4. Click the **Next Step** button.

If at any point, you wish to abandon the import, click **Abandon this import**.

5. Populate the following fields:

FIELD	REQUIRED?	DESCRIPTION
Name	Υ	Enter the name of your import file.
Source	Υ	Select a Source from the dropdown menu provided.
		You can also click on Add a New Source if the desired source is not listed in the dropdown menu
Select a status	Υ	Select a Status to be applied to the imported objects.
Add attributes	N	Select Attributes to be assigned to the imported objects.
Add comment	N	Add a comment to the imported objects.
Add	N	Add Relationships for the imported objects.
relationships If you ent found, you the new of specific of correspondents.		If you enter an object name that is not found, you can click the Create link to add the new object. If you limit your search to a specific object type, you are linked to the corresponding form. For example, if you limit your search to Adversaries, the Create



link opens the Add An Adversary form. If you leave the Limit search to field set to All Objects, you can select the object type you want to create from a drop-down list.

Tags N Enter any **Tags** that should be applied to the imported objects.

6. Click the **Submit** button.

New objects will become available in the Threat Library.



STIX 1.1.1, 1.2 Data Mapping

You can click on the expand icon located to top-right of this topic to expand and collapse all mapping tables below.

• > Threat Actors Mapping

STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Identity	Adversary.value	
ID	Adversary.attribute	STIX Reference ID
Title	Adversary.value	
Туре	Adversary.attribute	Туре
Timestamp	Adversary.published_at	
Description	Adversary.attribute	Description
Motivation	Adversary.attribute	Motivation
Sophistication	Adversary.attribute	Sophistication
Intended_Effect	Adversary.attribute	Intended Effect
Role	Adversary.attribute	Role
Confidence	Adversary.attribute	Confidence
Handling	Adversary.tlp	
Observed_TTPs	TTP	



STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Associated_Actors	Adversary	
Associated_Campaigns	Campaign	

• >Indicators Mapping

STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Title	Indicator.attribute	Indicator Title
ID	Indicator.attribute	STIX Reference ID
Timestamp	Indicator.published_at	
Туре	Indicator.attribute	Indicator Type
Description	Indicator.attribute	Description
Short Description	Indicator.attribute	Short Description
Producer	Indicator.source	
Observable	Indicator	
Indicated_TTP	TTP	
Kill_Chain_Phases	Indicator.attribute	Kill Chain Phase
Likely_Impact	Indicator.attribute	Likely Impact
Suggested_COAs	Course of Action	
Handling	Indicator.tlp	



STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Confidence	Indicator.attribute	Confidence
	Indicator.attribute.source	
Related_Observables		
Related_Indicators	Indicator	
Related_Campaigns	Campaign	
	Signature	
	Signature.type = "Snort"	
	Signature.value	
	Indicator.source	
	Course of Action	
	Indicator.attribute	Start Time
	Indicator.attribute	End Time
	Indicator.published_at	

• >Exploit Target Mapping

STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Title	Exploit Target.value	
ID	Exploit Target.attribute	STIX Reference ID



STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Description	Exploit Target.attribute	Description
Short Description	Exploit Target.attribute	Short Description
Weakness	Exploit Target.attribute	CWE ID
Weakness	Exploit Target.attribute	Weakness Description
Configuration	Exploit Target.attribute	CCE ID
Configuration	Exploit Target.attribute	Configuration Description
Configuration	Exploit Target.attribute	Configuration Short Description
Vulnerability	Exploit Target.attribute	CVE ID
Potential_COAs	Course of Action	
Related_Exploit_Targets	Exploit Target	

• > Observables Mapping

STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
ID	Indicator.attribute	STIX Reference ID
	Indicator.attribute	Description
	Indicator.type	IP Address
	Indicator.value	



STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
	Indicator.type	Filename
	Indicator.value	
	Indicator.type	File Path
	Indicator.value	
	Indicator.attribute	File Size
	Indicator.attribute	File Format
	Indicator.attribute	Packer
	Indicator.type	MD5
	Indicator.type	SHA-256
	Indicator.type	SHA-1
	Indicator.type	SHA-512
	Indicator.value	
	Indicator.type	SSDEEP
	Indicator.value	
	Indicator.type	FQDN
	Indicator.value	



STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
	Indicator.type	URL
	Indicator.value	
	Indicator.type	Email Subject
	Indicator.value	
	Indicator.type	Email Address
	Indicator.value	
	Indicator.type	IP Address
	Indicator.value	
	Indicator.type	User-agent
	Indicator.value	
	Indicator.type	Filename
	Indicator.value	
	Indicator.type	Mutex
	Indicator.value	
	Indicator.attribute	Port
	Indicator.attribute	Protocol



STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
	Object.Description	
	Spearphish.value	
	Indicator.type	Registry Key
	Indicator.value	
	Indicator.attribute	Hive

• > Campaigns Mapping

STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Title	Campaign.value	
ID	Campaign.attribute	STIX Reference ID
Description	Campaign.attribute	Description
Short Description	Campaign.attribute	Short Description
Timestamp	Campaign.started_at	
Names	Campaign.attribute	Alias
Status	Campaign.attribute	Status
Intended_Effect	Campaign.attribute	Intended Effect
Confidence	Campaign.attribute	Confidence
Activity	Campaign.attribute	Activity



STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Related TTPs	TTP	
Related Incidents	Incident	
Attribution	Adversary	
Associated_Campaigns	Campaign	

• > Courses of Action Mapping

STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Title	Course of Action.value	
ID	Course of Action.attribute	STIX Reference ID
Description	Course of Action.attribute	Description
Stage	Course of Action.attribute	Stage
Objective	Course of Action.attribute	Objective
Objective Confidence	Course of Action.attribute	Objective Confidence
Туре	Course of Action.attribute	Туре
Short Description	Course of Action.attribute	Short Description
Parameter_Observables	Indicator	
Impact	Course of Action.attribute	Impact
Cost	Course of Action.attribute	Cost



STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Efficacy	Course of Action.attribute	Efficacy
Related_COAs	Course of Action	
Incidents Mapping STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Title	Incident.value	
ID	Incident.attribute	STIX Reference ID
Timestamp	Incident.published_at	
Description	Incident.attribute	Description
Categories	Incident.attribute	Category
First Malicious Action	Incident.attribute	First Malicious Action
Initial_Compromise	Incident.attribute	Initial Compromise
First_Data_Exfiltration	Incident.attribute	First Data Exfiltration
Incident_Discovery	Incident.attribute	Incident Discovery
Incident_Opened	Incident.attribute	Incident Opened
Incident_Opened	Incident.started_at	
Containment_Achieved	Incident.attribute	Containment Achieved
Restoration_Achieved	Incident.attribute	Restoration Achieved



STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Incident_Reported	Incident.attribute	Incident Reported
Incident_Closed	Incident.attribute	Incident Closed
Incident_Closed		
Coordinator	Incident.attribute	Coordinator
	Incident.attribute	Coordinator
Reporter	Incident.attribute	Reporter
	Incident.attribute	Reporter
Responder	Incident.attribute	Responder
	Incident.attribute	Responder
Victim	Incident.attribute	Victim
	Incident.attribute	Victim
Related Indicators	Indicator	
Related Observables	Indicator	
Leveraged_TTPs	TTP	
Intended_Effect	Incident.attribute	Intended Effect
COA_Requested	Course of Action	



STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
COA_Taken	Course of Action	
Confidence	Incident.attribute	Confidence
Attributed_Threat_Actors	Adversary	
Discovery_Method	Incident.attribute	Discovery Method
Related_Incidents	Incident	

• >TTP Mapping

STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Title	TTP.value	
ID	TTP.attribute	STIX Reference ID
Description	TTP.attribute	Description
Handling	TTP.tlp	
Kill_Chain_Phases	TTP.attribute	Kill Chain Phase
Intended_Effect	TTP.attribute	Intended Effect
	TTP.attribute	CAPEC ID
Behavior	TTP.attribute	Attack Pattern
	TTP.attribute	Attack Pattern Description
	TTP.attribute	Attack Pattern Short Description



STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
	TTP.attribute	Malware Type
	TTP.attribute	Malware Name
	TTP.attribute	Malware Description
	TTP.attribute	Malware Short Description
	TTP.attribute	Malware Detection Vendor
	TTP.attribute	Malware Family
	TTP.attribute	Exploit
	TTP.attribute	Exploit Description
	TTP.attribute	Exploit Short Description
Exploit_Targets	Exploit Target	
Related_TTPs	TTP	
Resources	TTP.attribute	Tool
	TTP.attribute	Tool
	TTP.attribute	Tool Type
	TTP.attribute	Tool Description
	TTP.attribute	Tool Short Description



STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
	TTP.attribute	Infrastructure Type
	TTP.attribute	Infrastructure
	TTP.attribute	Infrastructure Short Description
	TTP.attribute	Infrastructure Description
	Indicator	
	TTP.attribute	Persona
Victim Targeting	TTP.attribute	Victim Name
	TTP.attribute	Victim <ciq identity="" name=""></ciq>
	TTP.attribute	Targeted Systems
	TTP.attribute	Targeted Information
	Indicator	

• >CIQ Identity Mapping

STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Party Name	Object.attribute	Name
Organization Name	Object.attribute	Organization
Industry Sector	Object.attribute	Industry
Nationality	Object.attribute	Nationality



STIX FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Languages	Object.attribute	Language
Address	Object.attribute	Country
Email Address	Object.attribute	E-Mail Address
Chat Handle	Object.attribute	Chat Handle
Phone	Object.attribute	Phone



STIX2.0 Data Mapping

You can click on the expand icon located to top-right of this topic to expand and collapse all mapping tables below.

• > Attack Patterns Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
created	Attack Pattern.Published_at	
description	Attack Pattern.Attribute	Description
external_references[]	See External References	
kill_chain_phases.[]e	See Kill Chain Table	
modified	Attack Pattern.Attribute	Modified At
name	Attack Pattern.Value	
revoked (if revoked == true)	Attack Pattern.Attribute	Revoked
labels	Attack Pattern.Attribute	Label

• > Threat Actors Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
aliases	Adversary	* The Adversary created will have all the same attributes and published_at as the base Attribute. All alias Adversaries will be inter-related



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
created	Adversary.Published_At	
goals	Adversary.Attribute	Goal
labels	Adversary.Attribute	Label
modified	Adversary.Attribute	Modified At
name	Adversary.Value	
primary_motivation	Adversary.Attribute	Primary Motivation
resource_level	Adversary.Attribute	Resource Level
roles	Adversary.Attribute	Role
secondary_motivation	Adversary.Attribute	Secondary Motivation
sophistication	Adversary.Attribute	Sophistication
revoked (if revoked == true)	Adversary.Attribute	Revoked
external_references[]	See External References	
personal_motivations	Adversary.Attribute	Personal Motivation

• >Indicators Mapping



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
created	Signature.Published_at	
description	Signature.Description	
external_references[]	See External References	
labels	Signature.Attribute	Label
modified	Signature.Attribute	Modified At
name	Signature.Name	ThreatQ will default to using Indicator Pattern as the signature name if a name is not provided.
pattern	Signature.Value	
	Signature.Type	Indicator Pattern
valid.from	Signature.Attribute	Valid From
valid.until	Signature.Attribute	Valid Until
revoked (if revoked == true)	Signature.Attribute	Revoked
kill_chain_phases.[]	See Kill Chain Table	

ThreatQ Indicator and / or Event objects based on the Observables Mapping may be derived from the pattern field and related back to the resulting Signature.



• > Indentities Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
contact_information	Identity.Contact_Information	
created	ldentity.Published_at	
description	Identity.Description	
external_references[]	See External References	
identity_class	Identity.Attribute	Identity Class
modified	Identity.Attribute	Modified At
name	Identity.Value	
sectors	Identity.Attribute	Sector
labels	Identity.Attribute	Label
revoked (if revoked == true)	Identity.Attribute	Revoked

• > Observables Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
created	Observable.Published_at	
modified	Observable.Attribute	Modified At
revoked (if revoked == true)	Observable.Attribute	Revoked



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
external_references	Observable.Attribute	External Reference See External References.
number_observed	Observable.Attribute	Number Observed
objects[]		Specifies Cyber Observable Objects representing this observation. See the tables below for parsing details.

• > Artifact Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: artifact	Indicator.Type	URL
mime_type	Indicator.Attribute	MIME Type
url	Indicator.Value	
hashes{}	Indicator.relationship	
hashes{}.key	Indicator.Type	MD5 / SHA-1 / SHA-256 / SHA-384 / SHA-512 / Fuzzy Hash
hashes{}.value	Indicator.Value	

• >Automous System Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: autonomous- system	Indicator.Type	ASN



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
number	Indicator.Value	
name	Indicator.Attribute	Name
rir	Indicator.Attribute	Regional Internet Registry

• > Directory Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: directory	Indicator.Type	File Path
path	Indicator.Value	
path_enc	Indicator.Attribute	Path Encoding
created	Indicator.Attribute	Created At
accessed	Indicator.Attribute	Last Accessed
contains_refs	Indicator.relationship	

• > Domain-Name Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: domain-name	Indicator.Type	FQDN
value	Indicator.Value	
resolves_to_refs[]	Indicator.relationship	

• > Email Addr Mapping



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: email-addr	Indicator.Type	Email Address
display_name	Indicator.Attribute	Display Name
value	Indicator.Value	
belongs_to_ref[]	Indicator.relationship	

• >Email Message Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: email-message	Event.Type Indicator.Type	Spearphish Email Subject
subject**	Event.Title Indicator.Value	
is_multipart	Indicator.Attribute	Is Multipart
date (if parsing as an event)* sent date (if parsing as an indicator)	Event.happened_at Indicator.Attribute	
content_type	Indicator.Attribute	Content Type
from_ref	Event.Relationship Indicator.Relationship	From
sender_ref	Event.Relationship Indicator.Relationship	Sender



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
to_refs	Event.Relationship Indicator.Relationship	То
cc_refs	Event.Relationship	СС
bcc_refs	Event.Relationship Indicator.Relationship	BCC
received_lines	Event.Attribute Indicator.Attribute	Received Lines
additional_header_fields	Event.Attribute Indicator.Attribute	Additional Header - {key} An attribute is created for each key-value pair of the additional_header_fields object.
body	Event.Attribute Indicator.Attribute	Body
body_multipart[].body_raw_ref***	Indicator	Filename
raw_email_ref	Event.Relationship Indicator.Relationship	
* To parse an event from an email n field.	nessage, the email must ha	ave a date and subject



STIX 2.0 FIELD

THREATQ FIELD MAPPING

THREATQ NAME

** To parse an indicator from an email message, the email must contain a **subject** field.

*** If an object in body_multipart has a body field (body_multipart[].body), an attribute is created. The attribute's name is "Body Multipart" and the attribute's value is in the format "Content Type: {body_multipart[].content_type}, Content Disposition: {body_multipart[].content_disposition}, Body: {body_multipart[].body}".

Note: Parsing both an indicator and event from an email message will relate the two objects .

• File Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: file	Indicator.Type	Filename
size	Indicator.Attribute	File Size
hashes{}		
hashes{}.key	Indicator.Type	MD5 / SHA-1 SHA-256 / SHA-384 / SHA-512 / Fuzzy Hash
hashes{}.value	Indicator.Value	
name	Indicator.Value	
name_enc	Indicator.Attribute	File Name Encoding



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
magic_number_hex	Indicator.Attribute	Magic Number Hex
mime_type	Indicator.Attribute	MIME Type
created	Indicator.Attribute	Created At
accessed	Indicator.Attribute	Last Accesse
parent_directory_ref	Indicator.Relationship	
is_encrypted	Indicator.Attribute	Encrypted
encryption_algorithm	Indicator.Attribute	Encryption Algorithm
decryption_key	Indicator.Attribute	Decryption Key
contains_refs[]	Indicator.Relationship	
content_ref	Indicator.Relationship	
extensions.archive-ext.contains_refs[]	Indicator.Relationship	
extensions.archive-ext.version	Indicator.Attribute	Archive Version
extensions.archive-ext.comment	Indicator.Attribute	Archive File Comment
extensions.ntfs-ext.sid	Indicator.Attribute	Security ID



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
extensions.ntfs- ext.alternate_data_streams[].hashes{}		
extensions.ntfs- ext.alternate_data_streams[].hashes{}.key	Indicator.Type	MD5 / SHA-1 SHA-256 / SHA-384 / SHA-512 / Fuzzy Hash
extensions.ntfs- ext.alternate_data_streams[].hashes{}.value	Indicator.Value	
extensions.ntfs- ext.alternate_data_streams[].name	Indicator.Attribute	Alternate Da Stream Nam
extensions.ntfs- ext.alternate_data_streams[].size	Indicator.Attribute	Alternate Da Stream Size
extensions.pdf-ext.version	Indicator.Attribute	PDF Specification Version
extensions.pdf-ext.is_optimized	Indicator.Attribute	PDF Is Optimized
extensions.pdf-ext.document_info_dict{}.key/ value	Indicator.Attribute	Formatted as 'PDF {key.title()}'
extensions.pdf-ext.pdfid0	Indicator.Attribute	PDF First File Identifier
extensions.pdf-ext.pdfid1	Indicator.Attribute	PDF Second File Identifie



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
extensions.raster-image-ext.image_height	Indicator.Attribute	Image Heigh
extensions.raster-image-ext.image_width	Indicator.Attribute	lmage Width
extensions.raster-image-ext.bits_per_pixel	Indicator.Attribute	Image Bits Pe Pixel
extensions.raster-image- ext.image_compression_algorithm	Indicator.Attribute	lmage Compressior Algorithm
extensions.raster-image-ext.exif_tags{}.key/ value	Indicator.Attribute	Formatted as 'Image EXIF {key.title()}'
extensions.windows-pebinary-ext.pe_type	Indicator.Attribute	Executable Extension Type
extensions.windows-pebinary-ext.imphash	Indicator.Attribute	Executable Imphash
extensions.windows-pebinary- ext.machine_hex	Indicator.Attribute	Target Machine Hex
extensions.windows-pebinary- ext.number_of_sections	Indicator.Attribute	PE Binary Section Cour
extensions.windows-pebinary- ext.time_date_stamp	Indicator.Attribute	PE Binary Created Date
extensions.windows-pebinary- ext.pointer_to_symbol_table_hex	Indicator.Attribute	Symbol Table Hex Offset



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
extensions.windows-pebinary- ext.number_of_symbols	Indicator.Attribute	PE Binary Symbol Table Size
extensions.windows-pebinary- ext.size_of_optional_header	Indicator.Attribute	PE Binary Optional Header Size
extensions.windows-pebinary- ext.characteristics_hex	Indicator.Attribute	PE Binary Characteristi Hex
extensions.windows-pebinary- ext.file_header_hashes{}		
extensions.windows-pebinary- ext.file_header_hashes{}.key	Indicator.Type	MD5 / SHA-1 SHA-256 / SHA-384 / SHA-512 / Fuzzy Hash
extensions.windows-pebinary- ext.file_header_hashes{}.value	Indicator.Value	
extensions.windows-pebinary- ext.optional_header.magic_hex	Indicator.Attribute	PE Binary Magic Hex
extensions.windows-pebinary- ext.optional_header.major_linker_version	Indicator.Attribute	PE Binary Major Linker Version
extensions.windows-pebinary- ext.optional_header.minor_linker_version	Indicator.Attribute	PE Binary Minor Linker Version



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
extensions.windows-pebinary- ext.optional_header.size_of_code	Indicator.Attribute	PE Binary Code Size
extensions.windows-pebinary- ext.optional_header.size_of_initialized_data	Indicator.Attribute	PE Binary Initialized Data Size
extensions.windows-pebinary- ext.optional_header.size_of_uninitialized_data	Indicator.Attribute	PE Binary Uninitialized Data Size
extensions.windows-pebinary- ext.optional_header.address_of_entry_point	Indicator.Attribute	PE Binary Memory Address Entr Point
extensions.windows-pebinary- ext.optional_header.base_of_code	Indicator.Attribute	PE Binary Base Code Memory Address
extensions.windows-pebinary- ext.optional_header.base_of_data	Indicator.Attribute	PE Binary Base Data Memory Address
extensions.windows-pebinary- ext.optional_header.image_base	Indicator.Attribute	PE Binary Base Image Memory Address
extensions.windows-pebinary- ext.optional_header.section_alignment	Indicator.Attribute	PE Binary Section



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
		Alignment Bytes
extensions.windows-pebinary- ext.optional_header.file_alignment	Indicator.Attribute	PE Binary Image File Alignment Bytes
extensions.windows-pebinary- ext.optional_header.major_os_version	Indicator.Attribute	Windows OS Major Versio
extensions.windows-pebinary- ext.optional_header.minor_os_version	Indicator.Attribute	Windows OS Minor Versio
extensions.windows-pebinary- ext.optional_header.major_image_version	Indicator.Attribute	lmage Major Version
extensions.windows-pebinary- ext.optional_header.minor_image_version	Indicator.Attribute	lmage Minor Version
extensions.windows-pebinary- ext.optional_header.major_subsystem_version	Indicator.Attribute	Subsystem Major Versio
extensions.windows-pebinary- ext.optional_header.minor_subsystem_version	Indicator.Attribute	Subsystem Minor Versio
extensions.windows-pebinary- ext.optional_header.win32_version_value_hex	Indicator.Attribute	Win32 Versio Hex
extensions.windows-pebinary- ext.optional_header.size_of_image	Indicator.Attribute	lmage Byte Size



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
extensions.windows-pebinary- ext.optional_header.size_of_headers	Indicator.Attribute	PE Binary Combined Header Size
extensions.windows-pebinary- ext.optional_header.checksum_hex	Indicator.Attribute	PE Binary Checksum Hex
extensions.windows-pebinary- ext.optional_header.subsystem_hex	Indicator.Attribute	PE Binary Required Subsystem Hex
extensions.windows-pebinary- ext.optional_header.dll_characteristics_hex	Indicator.Attribute	DLL Characteristi Hex
extensions.windows-pebinary- ext.optional_header.size_of_stack_reserve	Indicator.Attribute	Reserved Stack Size
extensions.windows-pebinary- ext.optional_header.size_of_stack_commit	Indicator.Attribute	Stack Comm Size
extensions.windows-pebinary- ext.optional_header.size_of_heap_reserve	Indicator.Attribute	Heap Space Reserve Size
extensions.windows-pebinary- ext.optional_header.size_of_heap_commit	Indicator.Attribute	Heap Space Commit Size
extensions.windows-pebinary- ext.optional_header.loader_flags_hex	Indicator.Attribute	Loader Flags Hex
extensions.windows-pebinary- ext.optional_header.number_of_rva_and_sizes	Indicator.Attribute	Number of RVA and Size



	STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
	extensions.windows-pebinary- ext.optional_header.hashes{}		
	extensions.windows-pebinary- ext.optional_header.hashes{}.key	Indicator.Type	MD5 / SHA-1 SHA-256 / SHA-384 / SHA-512 / Fuzzy Hash
	extensions.windows-pebinary- ext.optional_header.hashes{}.value	Indicator.Value	
	extensions.windows-pebinary- ext.sections[].hashes{}		
	extensions.windows-pebinary- ext.sections[].hashes{}.key	Indicator.Type	MD5 / SHA-1 SHA-256 / SHA-384 / SHA-512 / Fuzzy Hash
	extensions.windows-pebinary- ext.sections[].hashes{}.value	Indicator.Value	
	extensions.windows-pebinary- ext.sections[].name	Indicator.Attribute	PE Binary Section Nam
	extensions.windows-pebinary- ext.sections[].size	Indicator.Attribute	PE Binary Section Size
	extensions.windows-pebinary- ext.sections[].entropy	Indicator.Attribute	PE Binary Section Entropy
• 1	>IPv/A Manning		

• >IPv4 Mapping



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: ipv4-addr	Indicator.Type	CIDR Block (if value contains a / and does not end with /32) IP Address (if the value ends with /32, the /32 is omitted and reported as an IP Address)
value	Indicator.Value	
resolves_to_refs[]	Indicator.Relationship	
belongs_to_refs[]	Indicator.Relationship	

• >IPv6 Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: ipv6-addr	Indicator.Type	IPv6 Address
value	Indicator.Value	
resolves_to_refs[]	Indicator.Relationship	
belongs_to_refs[]	Indicator.Relationship	

• >MAC Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: mac-addr	Indicator.Type	MAC Address
value	Indicator.Value	

• >Mutex Mapping



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: mutex	Indicator.Type	Mutex
name	Indicator.Value	

• > URL Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: url	Indicator.Type	URL
value	Indicator.Value	

• > User Account Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: user-account	Indicator.Type	Username
user_id	Indicator.Attribute	User ID
account_login	Indicator.Value	
account_type	Indicator.Attribute	Account Type
display_name	Indicator.Attribute	Display Name
is_service_account	Indicator.Attribute	Is Service Account
is_privileged	Indicator.Attribute	Is Privileged Account
can_escalate_privs	Indicator.Attribute	Can Escalate Privileges
is_disabled	Indicator.Attribute	Is Disabled



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
account_created	Indicator.Attribute	Account Created
account_expires	Indicator.Attribute	Account Expires
password_last_changed	Indicator.Attribute	Password Last Changed
account_first_login	Indicator.Attribute	Account First Login
account_last_login	Indicator.Attribute	Account Last Login
extensions.unix- account-ext.gid	Indicator.Attribute	Account Group ID
extensions.unix- account-ext.groups[]	Indicator.Attribute	Account Group
extensions.unix- account-ext.home_dir	Indicator.Attribute	Account Home Directory
extensions.unix- account-ext.shell	Indicator.Attribute	Account Command Shell

• >Windows Registry Key Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
type: windows-registry- key	Indicator.Type	Registry Key
key	Indicator.Value	
values[].name	Indicator.Attribute	Registry Name



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
modified	Indicator.Attribute	Registry Modified At
creator_user_ref	Indicator.Relationship	

• > Campaigns Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
aliases	Campaign	
created	Campaign.Published_at	
description	Campaign.Description	
first_seen	Campaign.Started_at	
last_seen	Campaign.Ended_at	
modified	Campaign.Attribute	Modified At
name	Campaign.Value	
objective	Campaign.Objective	
revoked (if revoked == true)	Campaign.Attribute	Revoked
external_references[]	See External References	
labels	Campaign.Attribute	Label

• > Courses of Action Mapping



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
created	Course of Action.Published_at	
modified	Course of Action.Attribute	Modified At
name	Course of Action.Value	
description	Course of Action.Description	
action		
revoked (if revoked == true)	Course of Action.Attribute	Revoked
external_references[]	See External References	
labels	Course of Action.Attribute	Label

• >Intrusion Sets Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
aliases	Intrusion Set	
created	Intrusion Set.Published_at	
description	Intrusion Set.Description	
first_seen		
goals	Intrusion Set.Attribute	Goal
modified	Intrusion Set.Attribute	Modified At
name	Intrusion Set.Value	



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
primary_motivation	Intrusion Set.Attribute	Primary Motivation
resource_level	Intrusion Set.Attribute	Resource Level
secondary_motivations	Intrusion Set.Attribute	Secondary Motivation
external_references[]	See External References	
revoked (if revoked == true)	Intrusion Set.Attribute	Revoked
>Malware Mapping		
STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME

created Malware.Published_at	
description Malware.Description	
kill_chain_phases.[] See Kill Chain Table	
labels Malware.Attribute Label	
modified Malware.Attribute Modified A	Λt
name Malware.Value	
external_references[] See External References	
revoked (if revoked == true) Malware.Attribute Revoked	

• >Tools Mapping



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
created	Tool.Published_at	
modified	Tool.Attribute	Modified At
labels	Tool.Attribute	Label
name	Tool.Value	
revoked (if revoked == true)	Tool.Attribute	Revoked
external_references[]	See External References	
description	Tool.Description	
kill_chain_phases.[]	See Kill Chain Table	
tool_version	Tool.Attribute	Tool Version

• >Reports Mapping

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
created	Report.Published_at	
modified	Report.Attribute	Modified At
name	Report.Value	
description	Report.Description	
labels	Report.Attribute	Label
object_refs	Report.Relationship.Link	



STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
external_references[]	See External References	
revoked (if revoked == true)	Report.Attribute	Revoked
• > Sightings Mapping	TUDEATO FIELD MADDING	TUDEATO NAME
STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
count	Event.Attribute	Count
created	Event.published_at	
first_seen	Event.happened_at	
last_seen	Event.Attribute	Last Seen
observed_data_refs	Event.relationship.link	
sighting_of_ref	Event.relationship.link	
where_sighted_refs	Event.relationship.link	
revoked (if revoked == true)	Object.attribute	Revoked
	Event.name	STIX Sighting
	Event.type	Sighting
external_references[]	See External References	
modified	Event.Attribute	Modified



External References

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
Object.external_references[].source_name	Object.Attribute	External Reference*
Object.external_references[].external_id	Object.Attribute	External Reference*
Object.external_references[].description	Object.Attribute	External Reference*
Object.external_references[].url	Object.Attribute	External Reference*

^{*} Formatted as: {source_name} ({external_id}): {description} - {url}

Kill Chain Phrases

STIX 2.0 FIELD	THREATQ FIELD MAPPING	THREATQ NAME
kill_chain_phases[].kill_chain_name	Object.Attribute	Kill Chain Name
kill_chain_phases[].phase_name	Object.Attribute	Kill Chain Phrase



Tasks

ThreatQ allows you to create and assign tasks to yourself or other users in the platform.

Once tasks are included in your deployment, you can add contextual information and correlate them with Indicators, Events, Adversaries, Signatures, and Files. You can also add comments, change the task priority, change the task status, and delete the task.

Assigning a Task

Complete the following steps to assign a task in ThreatQ.

1. From the main menu, choose **Create > Task**.



The Add Task dialog box opens.

- 2. Enter a task Name.
- 3. Enter the assignee's email address in the **Assigned To** field.
- 4. Optionally, use the date picker to select a **Due Date**.
- 5. Select one of the following statuses:
 - To Do
 - In Progress
 - Review
 - Done
- 6. Select one of the following task priorities:
 - Low
 - Medium
 - High
- 7. Optionally, enter any **Associated Objects**.
- 8. Enter a **Description** for the task.
- 9. Click Save.

Managing Tasks

After a task is created, you can manage it on the task's Details page.



The following table describes the actions you can take to manage your tasks on a Task Details page.

ТО	YOU CAN
Change task priority	Choose the Priority drop-down and select a new priority.
Change task status	Choose the Status drop-down and select a new status.
Add Attributes, Comments, Relationships, and Sources	Choose the Add Context drop-down and select an item.
View and Add Comments	Choose Comments .
View the Audit Log	Choose Audit Log .



Threat Library

The ThreatQ Threat Library provides an organized and searchable index of threat intel system objects that have been ingested into the ThreatQ platform.

From the Threat Library, you can view system objects by type, search the Threat Library by Building Searches with Filter Sets, perform Bulk Actions on search results, and view Object Details.



Managing Your Library View

You can limit the object types displayed in your ThreatQ Threat Library view and configure which data columns will be displayed in your search results.


Selecting Object Type View

You can select which object types appear in your view of the Threat Library using the following methods:

The methods listed below will not be added to your filter set. See the Type Filters topic for details on how to add object type filtering to your filter sets.

Threat Library Navigation Menu:

1. Click on the Threat Library navigation dropdown and select an Object Type or Browse All.



The Advanced Results page opens with the applied object type filter.




You can also access the Data Controls from this menu.

Object Type Left-Hand Menu



You can use the left-hand menu of the Threat Library to select view specific system object types.

You can either use the **Object Type** dropdown list or click directly on a object type listed in the menu.



Managing Library Columns

You can choose which columns to display in your Threat Library view.

To select columns:


1. Navigate to the Threat Library page.



2. Choose Manage Columns.

Threat Library

Threat Library



3. Select the columns you wish to display. Clear the columns you wish to hide.



Basic Search

The basic Search, located to the right of the **Create** button in the ThreatQ navigation, allows you to find objects you are looking for quickly, without having to browse through a large number of objects.

Basic Search allows you to search for all objects in the system: indicators, events, adversaries, files, signatures, and so on. The search capability looks at high level aspects of each object, including:


- Indicators (network or host)
- · Attachment titles, hashes, keywords
- Attributes
- Adversary name
- · Event title

If searching for google.com, the following indicators will also be returned:

- www.google.com (FQDN)
- analytic.google.com (FQDN)
- www.google.com/analytic (URL)
- analytic@google.com (email address)


Performing a Basic Search

1. Choose the Search icon.






The Search dialog box appears.



- 2. Use the **Limit Search** dropdown to filter your search to a specific object type.
- 3. Enter the search criteria.

The Search field provides type ahead suggestions, if any, based on what you have typed. Portions of the suggestions that match your search criteria will be highlighted in bold.



- 4. Select the desired result.
 - If you do not retrieve any search results, we recommend trying the Threat Library advanced search.
 - If there is only one result, the object details page appears.



Wildcards and Symbols in Searches

During a search, you may use a percent sign (%) to match characters in a string. The percent wildcard specifies that any characters can appear in multiple positions represented by the wildcard. For example, specifying net% matches network, netware, netscape, and so on.


Here are a number of examples showing search terms with percent wildcards:

SEARCH QUERY	DESCRIPTION
% panda	Finds any adversaries and indicators with <name> panda</name>
%ear	Finds any character string that ends with "ear," such as bear
%panda%	Finds any character string that has panda in any position
panda%	Finds any character string that begins with panda
pan%a	Finds any character string that has pan in the first three positions and ends with an "a"


Creating an Object During a Basic Search

The Basic Search window gives you the option to add a new object. If you enter an object name that is not found, you can click the **Create** link to select the object type from a dropdown list and add the new object. In addition, if you limit a basic search to a specific object type, you are linked to the corresponding form. For example, if you limit your search to Adversaries, the **Create** link opens the **Add An Adversary** form.





If you leave the **Limit search to** field set to All Objects, you can select the object type you want to create from a drop-down list.






Building Searches with Filter Sets

Filter Sets allow you to create multiple sets of filters that can be applied to the threat library at the same time using AND/OR logic. You can also save your Filter Sets using the Save Search option - see the Saving Searches section in the Managing Search Results topic for more details.

Adding Filter Sets

- 1. Use the **NOT** checkbox to determine if the filters in the initial filter set will be used to include or exclude Threat Library objects.
- 2. Select one or more filters for the search.




You can use the search box provided at the top of the filters dropdown to narrow down the list of available filters.


3. Click on Add Another Filter Set.



A new Filter Set table will load below the first set.




- 4. Use the **Not** checkbox to determine if the filters in the new filter set will be used to include or exclude Threat Library objects.
- 5. Use the Filters dropdown next to the new filter set to add filters.





6. Click on the **And/Or** dropdown to set the **And/Or** logic for the Filter Sets. See the And/Or Order of Operations topic for more details.






Repeat steps 3-6 to add additional filter sets.

Deleting Filter Sets

- eal Deleting a Filter Set removes it from the search results and cannot be undone.
- 1. Click on the delete icon located next to the right of the Filters dropdown.







You can click on **Clear Filters**, located above the filter sets, to remove all filter sets from the current search.

And/Or Order of Operations

Filter Set AND/OR logic follows the standard mathematical order of operations with ANDs being executed before ORs. The table below provides different scenarios and examples for Filter Sets.

SCENARIO	ORDER	EXAMPLE
Single AND	Filter 1 AND Filter 2	TOTAL CO. TOTAL
Single OR	Filter 1 OR Filter 2	
Single AND, Single OR	(Filter 1 AND Filter 2) OR Filter 3	
Multiple ANDs, Single OR	(Filter 1 AND Filter 2 AND Filter 3) OR Filter 4	Marie de la companya del companya de la companya de la companya del companya de la companya del la companya del la companya de la companya de la companya del la companya de la companya del la companya
Multiple ANDs, Multiple ORs	(Filter 1 AND Filter 2) OR (Filter 3 AND Filter 4)	



Context Filters


Context filters allow you to filter advanced search results by specific details associated with an object.

Filtering by Attribute

You can filter the Threat Library list to include or exclude objects with a specific attribute.

1. Click the **Filters** option and select either **With Attribute** or **Without Attribute**.

The Attribute Filter dialog box opens.



- 2. Select an Attribute Type.
- 3. Enter an **Attribute Value** associated with the **Attribute Type**. When you apply a **With Attribute** filter, you can use wildcard values to more easily locate indicators. The Value field supports the following search methods:

SEARCH TYPE	SEARCH QUERY	SEARCH RESULTS
Exact Match	us	US only
Ends With	*us or %us	US and Lazarus
Begins With	us* or us%	US, USBferry, and USBStealer
Value Contains	*us* or %us%	US, USBferry, USBStealer, Lazarus, and Dust Storm





Click the **Plus** icon to the right of the dialog box to add another attribute and repeat steps 2-3. This step is optional.

4. Click the Add button.

The filters are applied to the search results.

Using Multiple Attribute Filters

The Match Any/All toggle option allow you to configure the filter to include objects that either fit one attribute filter or all. The Any option is selected by default. This means the filter displays results that fit any of the attribute filters. The All option means the filter displays results that fit all attribute filters.

Example:

ANY - Match Toggle Selection

Setting	Field	Value
Filter A	Attribute Type	Attack Phase
	Attribute Value	C2
Filter B	Attribute Type	Severity
	Attribute Value	High
Filter Options	Any/All Toggle	Any
Result	Search Results are filtered to include/C2 OR Severity: High attributes.	exclude objects with Attack Phase:

ALL - Match Toggle Selection



Setting	Field	Value
Filter A	Attribute Type	Attack Phase
	Attribute Value	C2
Filter B	Attribute Type	Severity
	Attribute Value	High
Filter Options	Any/All Toggle	All
Result	Search Results are filtered to include/exclude objects with Attack Phase: C2 AND Severity: High attributes.	

Attribute Common Scenarios

> Applying a "With Attribute" filter (All items with an Attribute Type and Value)

- 1. User clicks on the **Threat Library** tab and selects on the **Indicators** tab.
- 2. User clicks on the **Filters** button and select **With Attribute**.

The Attribute Filter dialog box opens.

- 3. User selects **Attack Pattern** as the **Attribute Type** and **C2** as the **Attribute Value**.
- 4. User clicks on Add.

The User will now see a search parameter **With Attribute** with **Attack Pattern: C2** listed. The search results update to show all Indicators with an attribute of **Attack Pattern: C2**.

> Applying a "Without Attribute" filter (All items without an Attribute Type and Value)

- 1. User clicks on the **Threat Library** tab and selects on the **Indicators** tab.
- 2. User clicks on the **Filter** button and select **Without Attribute**.

The Attribute Filter dialog box opens.

3. User selects **Attack Pattern** as the **Attribute Type** and **C2** as the **Attribute Value**.



4. User clicks on Add.

The User will now see a search parameter **With Attribute** with **Attack Pattern: C2 listed**. The search results update to show all Indicators without an attribute of **Attack Pattern: C2**.

> Applying a "Without Attribute" filter (All items Without a specific Attribute Type with any Value)

- 1. User clicks on the **Threat Library** tab and selects on the **Indicators** tab.
- 2. User clicks on the **Filters** button and select **Without Attribute**.

The Attribute Filter dialog box opens.

- 3. User selects Attack Pattern as the Attribute Type and leave the Attribute Value blank.
- 4. User clicks on **Add**.

The User will now see a search parameter **Without Attribute** with **Attack Pattern** listed. The search results update to show all Indicators that do not have an **Attribute Type** of **Attack Pattern** assigned to them.

>Applying keyword filters then applying a "With Attribute" filter

- 1. User clicks on the **Threat Library** tab and selects on the **Indicators** tab.
- 2. User searches for keyword: **demo**.

The User will see a search parameter listed Keyword: "demo" and the results update to show only indicators that mention demo.

3. User clicks on the **Filters** button and select **With Attribute**.

The Attribute Filter dialog box opens.

- 4. User selects **Attack Pattern** as the **Attribute Type** and **C2** as the **Attribute Value**.
- 5. User clicks on **Add**.

The User will now see a search parameter **With Attribute** with **Attack Pattern: C2** listed. The search results will update to show all Indicators that mention the keyword **demo AND** have an attribute of **Attack Pattern: C2**.

> Editing multiple attributes that were applied as part of the search parameters

1. User clicks on the **Threat Library** tab and navigates to the **Indicators** tab.



2. User clicks on the **Filter** button and select **With Attribute**.

The Attribute Filter dialog box opens.

- 3. The User specifies two attributes:
 - Attack Pattern:C2
 - Severity: High
- 4. User clicks on Add.

The User will now see two search parameters under the **With Attribute** section - **Attack Pattern: C2** and **Severity: High**. The search results updates to show all Indicators with an attribute of **Attack Pattern: C2** and **Severity: High**. The search parameter for attributes is defaulted to Any. This indicates that objects with an attribute of **Attack Pattern: C2** or **Severity: High** are displayed.

5. User clicks on the **Filters** option and selects **With Attribute**.

A form will load with all applied filter attributes.

6. The User clears the **Attack Pattern's Attribute Value** field and clicks **Add**.

The User will now see two search parameters under the **With Attribute** section: **Attack Pattern: Any** and **Severity: High**. The search results updates to show all Indicators with an attribute type of **Attack Pattern OR Severity: High**.

>Add multiple attributes and toggle Match from Any to All

 User applies two attribute filters to the indicators results: Attack Phase: C2 and Severity: High.

The filtered results will display any indicators that has either of those attributes.

2. User clicks on the **Any/All** Match toggle button and select **All**.

The filtered results will display any indicator that has both of those attributes


Filtering by CIDR Block Range

You can filter Threat Library objects by a block of IP addresses using the CIDR block range filter. The CIDR Block Range filter allows you to specify a CIDR block with prefix and suffix for an IPv4 search.

1. Click the **Filters** option and select **CIDR block range**.



The Add a CIDR Block dialog box opens.




- 2. Enter the CIDR block in one of the following formats:
 - x.x.x.x/8
 - x.x.x.x/16
 - x.x.x.x/24
 - x.x.x.x/32
- 3. Click **Add CIDR Block** to apply the filter.

Filtering by Value Contains

You can filter Threat Library objects by a specific value or string within the value using the Value Contains filter.

1. Click the **Filters** option and select **Value Contains**.

The Contains dialog box opens.



2. Select an **Object**, enter a **Value**, and click **Add** to apply the filter.




Filtering by List of Indicators

The List of Indicators Filter option allows you to filter the Threat Library by pasting a list of indicators, in raw text.




The filter will return indicators that are an exact match. It does not return partial matches.

1. Click the **Filters** option and select **List of Indicators**.



The List of Indicators dialog box opens.





2. Enter or paste your list of indicators into the textbox provided.





The accepted list format is one indicator per line.

3. Click **Add** to apply the filter.

Filtering by Keyword

You can filter the Threat Library items on the Advanced Search by keyword.

- 1. Click the Filters option and select either Keyword to access the Filter by Keyword window.
- 2. Enter a keyword.
- 3. Click the Add button.
- 4. To add more keywords, repeat steps 1 through 3.
- 5. If you add more than one keyword, you can specify a **Must Match** setting of:
 - $\,{}^{\circ}\,$ ANY Search results include objects that include any of the keywords.
 - ALL Search results include objects that include all of the keywords.
- 6. Click the **X** for each filter to remove it or select **Clear All Filters** to remove all filters The following list of fields are all searched against for any matches of keywords:
 - Source Names

 Spearphish Value (for Events of Type 'Spearphish')

Attribute Names

Indicator Type Name



Attribute Values	· Indicator Status Name
· Comments	Indicator Value
∘ Tags	Indicator Class
Adversary Name	Indicator Description
 Adversary Description 	 Signature Name
• File/Attachment Name	 Signature Description
• File/Attachment Title	 Signature Value
 File/Attachement Type Name 	 Signature Has
 File/Attachment Content-Type Name 	 Signature Type Name
• File/Attachment Hash	 Signature Status Name
 File/Attachment Description 	Task Name
• File/Attachment Contents	• Task Description
。Event Title	 Task Status Name
 Event Type Name 	 Task Assignee Source Name



Event Description


- Task Creator Source Name
- Spearphish Subject (for Events of Type 'Spearphish')

Filtering by Relationship

The Relationship Filter option allows you to filter the Threat Library by related objects. Using the Relationship filter, you can:

- Filter search results to include objects related to a specific object.
- Filter search results to include objects using multiple related object filters. You will also have the option to set the filter to include objects that fit one of the multiple filters or all.
- 1. Click the **Filters** option and select **Relationship**.

The Filter by Relationship dialog box opens.



- 2. Use the textbox provided to select an object.
- 3. Click **Add** to apply the filter.



The Match Any/All toggle option will allows you to configure the filter to include objects that either fit one related object filter or all. The Any option will be selected by default. This means the filter will display results that fit any of the related object filters. The All option means the filter will display results that fit all related object filters.



Examples:

ANY - Match Toggle Selection

Setting	Related Object
Filter A	ABC Indicator
Filter B	DEF Event
Filter Option	Any
Result	Search Results are filtered to include objects related to the ABC Indicator OR the DEF Event.

ALL - Match Toggle Selection

Setting	Related Object
Filter A	ABC Indicator
Filter B	DEF Event
Filter Option	All
Result	Search Results are filtered to include objects related to the ABC Indicator AND the DEF Event.




Filtering by Related Object Type

The **Related Object** filter allows you to filter search results by related object type. Using this filter, you can do the following:


- Filter search results that return related items linked to certain objects.
- Filter search results that return related items linked to certain object types.
- Apply a Value Contains filter to the results.
- 1. Click the Filters option and select Relationship Criteria.

The **Relationship Criteria** dialog box opens.






2. Use the text box to select your **Object** and **Type**.






Steps 3-4 are optional.

3. Click the **Filters** dropdown and select **Value Contains**.





4. Enter your desired value in the field provided.



5. Click **Apply** to filter.

Filtering by Score

You can filter indicators in the advanced search results by score.




This option is only available for indicators.

1. Navigate to the Advanced Search results page by selecting **Search > Advanced Search** then selecting **Indicators** from the left-hand object type menu.

You can also select **Threat Library > Indicators** from the main menu.



2. Click the **Filters** dropdown and select the **Indicator Score** filter option. The Indicator Score dialog row will load in the filter set.



- The scale offers a range of 1-10.
- 3. Adjust the score scale to filter the results.

Filtering by Scoring Range

You can move the two scale markers to select a scoring range.



Move the left marker to 6 and the right marker to 8 to filter the search results to include indicators with a score between 6 and 8.

Filtering by Specific Score

You can move the scale makers to the same scoring number to filter by a specific score.



Move the left and right markers to 8 to filter the search results to only include indicators with a score of 8.



Select the **Update Score** filter again or select **Clear** to remove the filter.




Filtering by Tags

Using the **Tags** filter allows you to filter search results based on tags applied to an object.

1. Click the **Filters** option and select **Tags**.

The Filter by Tag row opens.



- Select Add Tag.The Add Tag dialog box opens.
- 3. Use the supplied text field to select a tag.
- 4. Repeat steps 2-3 to apply multiple tag filters.



The Match Any/All toggle option will allows you to configure the filter to include objects that either fit one tag filter or all. The Any option will be selected by default. This means the filter will display results that fit any of the tag filters. The All option means the filter will display results that fit all tag filters.

Examples:

ANY - Match Toggle Selection

Setting Tag



Filter A	Phishing
Filter B	DDoS
Filter Option	Any
Result	Search Results are filtered to include items with either Phishing OR the DDoS tags.

ALL - Match Toggle Selection

Setting	Tag
Filter A	Phishing
Filter B	DDoS
Filter Option	All
Result	Search Results are filtered to include items with both Phishing AND DDoS tags.

Filtering by Source

The Source filter allows you to filter Threat Library search results by indicator source. You can also specify whether the filter applies to the object or attribute source.

- 1. Click the **Filters** option and select **Source**. The Filter by Source row opens.
- 2. Locate and select the source name you for your filter by scrolling through the drop-down list or entering the name in the Search for sources field.
- 3. Click the arrow next to Source to specify whether the filter references all sources or is restricted to object or attribute sources.



4. To continue adding sources to the filter, click the Add Source option and repeat step 2.



The Match Any/All toggle option will allows you to configure the filter to include objects that either fit one related object filter or all. The Any option will be selected by default. This means the filter will display results that fit any of the related object filters. The All option means the filter will display results that fit all related object filters.

Examples:

ANY - Match Toggle Selection

Setting	Source
Filter A	This Platform
Filter B	Domain Tools
Filter Option	Any
Result	Search Results are filtered to include objects with a source of This Platform OR Domain Tools.

ALL - Match Toggle Selection

Setting	Source
Filter A	This Platform
Filter B	Domain Tools
Filter Option	All



Result

Search Results are filtered to include objects with both This Platform **AND** Domain Tools as sources.

Filtering by TLP

Users can filter Threat Library search results by specific TLP color designations. For reference on Traffic Light Protocol (TLP), view the Traffic Light Protocol (TLP) topic.

The filter functions in two ways. First, the filter will be applied to the object's source TLP and will only return system objects that contain a source that matches the TLP values selected in the TLP filter. The filter will then limit source and attribute column data of the search results to only display data that matches the TLP filter.



TLP visibility must be enabled to use the TLP filter in the Threat Library search. See the Configure TLP Visibility section for more details.

1. Navigate to Threat Library.

The option to filter by TLP color designation will be located under the search bar and Filter Set option.



2. Use the **Limit by TLP** filter check boxes to select which TLP designations to apply to your search results.



If TLP Green is checked, only objects with any source of TLP Green will be returned in the search results.

From the Objects retrieved, the TLP filter also impacts the information returned in search results columns, including Sources and Attributes.

Sources - In the Sources column of the search results, only sources that match the selected TLP colors will be displayed.



Sources displayed before applying the TLP filter Sources displayed after applying the TLP filter

Attributes - In any displayed Attribute column of the search results, only attribute values with sources that match the selected TLP colors will be displayed.

SCENARIO	RESULTS DISPLAY
Attribute Contributors displayed before applying the TLP filter	According to
Attribute Contributors displayed after applying the TLP filter	Secretaria (march (m.) for the law (march (m.) for the law (m.)

Additional Notes:

- TLP filters can be stored as part of data collections, similar to other filter types.
- The TLP filter is a global filter in that it is applied across all object types and all filter sets for a given search query (i.e. it cannot be applied to individual object types or within individual filter sets).
- TLP filters impact the Threat Library CSV output and CSV results output will match those in the Threat Library results UI.
- In any displayed Attribute column of the search results, only attribute values with sources that match the selected TLP colors will be displayed.



Date Filters


Date filters allow you to filter advanced search results by date-related values.

Filtering by Date Created

Complete the following procedure to filter Advanced Search results by the date the objects were created.

1. Click on the **Filters** option and select **Date Created**.

The Date Created dialog box opens.



2. Select one of the following options to determine how the filter is applied:

OPTION	RESULT
is before	Search results include items before a selected date
is after	Search results include items after a selected date
is in the range of	Search results include items in a selected range of dates
is within the last	Search results include items within the selected number of days.

3. Use the controls to select date options based upon the selection in step 2.




4. Click Save.

Filtering by Last Modified

Complete the following procedure to filter Advanced Search results by the date objects were last modified.

1. Click on the **Filters** option and select either **Last Modified**.

The Last Modified dialog box opens.



2. Select one of the following options to determine how the filter is applied:

OPTION	RESULT
is before	Search results include items before a selected date
is after	Search results include items after a selected date
is in the range of	Search results include items in a selected range of dates
is within the last	Search results include items within the selected number of days.

- 3. Use the controls to select date options based upon the selection in step 2.
- 4. Click Save.




Filtering by Published Date




The Published Date is the date that an object was originally published by the source. This is not to be confused with when the object was ingested into ThreatQ.

1. Click on the **Filters** dropdown option for a filter set and select **Published Date**.



The Published Date dialog box opens.





- 2. Select the **Source** that published the object.
- 3. Select one of the following options to determine how the filter is applied:

OPTION	RESULT

published before	Search results include items before a selected date
published after	Search results include items after a selected date
published between	Search results include items in a selected range of dates
published within the last	Search results include items within the selected number of days.


- 4. Select **Date**, **Time**, and **Time Zone** for the filter to use.
- 5. Click Save.




Filtering by Source Ingest Time

The Source Ingest Time is the date that an object was ingested into ThreatQ.

1. Click on the Filters dropdown option for a filter set and select Source Ingest Time.



The Source Ingest Time dialog box opens.





2. Select the **Source** that published the object.

You have the option to select **Any Source**.

3. Select one of the following options to determine how the filter is applied:

OPTION	RESULT
created before	Search results include items before a selected date
created after	Search results include items after a selected date
created between	Search results include items in a selected range of dates
created within the last	Search results include items within the selected number of days.


- 4. Select **Date**, **Time**, and **Time Zone** for the filter to use.
- 5. Click Save.

Filtering by Expiration Date

You can narrow down the Indicators in your search results by the expiration date.

1. Click on the Filters dropdown option for a filter set and select Expiration Date.





The Expiration Date dialog box opens.

2. Select one of the following options to determine how the filter is applied:

OPTION	RESULT
is	Search results include the specified date.
is not	Search results exclude items from a range of dates.
is after	Search results include items after a selected date.
is before	Search results include items before a selected date.
is between	Search results include items in a selected range of dates.
is within the last	Search results include items within the selected number of days.
is within the next	Search results include items within a range of future dates.



OPTION RESULT

is protected from autofrom autofrom autoexpiration

RESULT

Search results include items that are protected from autofrom a

- 3. Select **Day**, **Month**, and **Year** for the filter to use.
- 4. Click **Submit**.



Status Filters

Status filters allow you to filter advanced search results an object's Status.



Only Indicators, Signatures, and Tasks can be filtered by their Status.

Filtering by Status

1. Click on the Filters dropdown and select **<Object Type>Status**.



The Status filter row will appear in the filter set.

2. Click on Add Status.



You can select multiple statuses using the check boxes.

The search results will update with the applied filter.



Tasks Filters

Tasks filters allow you to filter tasks based on their priority and to whom they are assigned.

Filtering Tasks by Assignment

You can filter tasks based on whom they are assigned to.


- 1. Click on the **Filters** option and select **Assigned To**.
- 2. Use the **Add User** dropdown to select the user.

Filter Set 1	
ASSIGNED TO	Add User ♥
Q Search	
☐ Amy Rose	
☐ Ivo Robotnik	
☐ John Apple	



Filtering Tasks by Due Date

1. Click on the **Filters** option and select **Due Date**.



The Due Date dialog box opens.



2. Select one of the following options to determine how the filter is applied:

OPTION	RESULT
is after	Search results include tasks with a due date after a selected date.
is before	Search results include tasks with a due date before a selected date.
is between	Search results include tasks with a due date that set between the selected range of dates.




OPTION	RESULT
ls within	Search results include tasks with a due date within the last user-
the last	specified number of days.
ls within	Search results include tasks with a due date within the next user-
the next	specified number of days.

3. Click Save.

Filtering Tasks by Priority

You can filter tasks based on their priority.

- 1. Click on the **Filters** option and select **Priority**.
- 2. Use the **Priority** dropdown and select **Add Priority**.







Filtering Tasks by Reported By

You can filter tasks based on who created it.

1. Click on the **Filters** option and select **Reported By**.




The Reported By Filter will appear in the filter set.





2. Click on the **Add User** option to select the user.





Type Filters

You can filter Indicators, Events, Signatures, and Files by specific types of each.

Filtering by Object Type

- Filter the Signature list to include YARA types only.
- 1. Click on the Filters dropdown and select **<Object Type>Type**.
 - The Type filter row will appear in the filter set.
- 2. Click on Add Type.
 - You can select multiple types using the check boxes.

The search results will update with the applied filter.



Managing Search Results


You can save your Threat Library searches as Data Collections for future use, integration workflows, and to be used with ThreatQ Custom Dashboards.




Integrations and custom dashboards use data collections and are affected if an associated data collection is deleted. Use caution when deleting a data collection.

Saving Searches as Data Collections

- 1. Perform a search on the Threat Library.
- 2. Click the Save As link.



The Save Data Collection dialog box opens.



3. Enter a name for the search in the Data Collection dialog box.




4. Click the **Save Data Collection** button.

The name of the data collection is displayed at the top of the page. As the data collection creator, you have owner-level permissions and are the only user who can view or edit the data collection. See the Sharing Data Collections section for information on allowing other users to access your data collection.



Loading Data Collections

- 1. Navigate to the Threat Library page.
- 2. Click the **Load Data Collection Search** option. The data collection window defaults to the All tab that lists all the data collections you own or to which you have view or edit access. The Owned By Me tab lists the data collections for which you are the owner. You can also locate a data collection by using the search field.




3. Select the data collection.

The data collection is displayed in the Threat Library page. The name of the data collection is listed at the top of the page.






If the data collection name is longer than forty characters, it is truncated with ellipses



- 4. Click the (1) icon to view:
 - Data collection name and owner
 - Date of the last change to the data collection
 - Dashboards or data feeds that use the data collection. You can click these items to access the corresponding dashboard or data feed.
 - The number of private dashboards that use the data collection





Modifying a Data Collection

Users with owner or editor permissions for a data collection can make changes to it.


- 1. Navigate to the Threat Library.
- 2. Load the data collection you want to change.
- 3. Enter your changes to the data collection.
- 4. Click the Save link.

Copying a Data Collection

When an owner or editor makes changes to a data collection, the Save As link gives him the option to create a new data collection that reflects these changes and leave the original data collection unchanged. For example, a user can add a filter to an existing Adversaries data collection to include only MITRE Enterprise ATT&CK sources, then save the new data collection as Adversaries - MITRE Enterprise.

- 1. Navigate to the Threat Library.
- 2. Load the data collection you want to copy.
- 3. Enter your changes to the data collection.
- 4. Click the Save As link.

The Save Data Collection window is displayed.



- 5. Enter the name of the new data collection.
- 6. Click the Save Data Collection button.

 ThreatQ creates your new data collection and displays it in the Threat Library page.




Renaming a Data Collection

Only the owner of a data collection can change its name.

- 1. Navigate to the Threat Library.
- 2. Load the data collection whose name you want to change.
- 3. Click the ① icon.
- 4. Click the \emptyset icon next to the data collection's name.
- 5. Enter the new name.
- 6. Click the v to save your change.

Sharing Data Collections

Owners and editors have the option to share a data collection with other users. However, only the data collection owner can remove a user's permissions. In addition, the Share(d) button displayed depends on your permission level and the sharing status of the data collection.




See the Sharing topic for more information on the user and group-level permissions you can assign to each data collection.

- 1. Navigate to the Threat Library.
- 2. Load the data collection you want to share.




3. Click the **Share** button.

The Sharing window allows you to select the user to which you want to grant access.




- 4. Click the arrow next to the <a> icon to select the user's permission level.
 - If you are granting access to all users, you must select the **Can View** option. You can only assign editing permission to individual users not to all users.
 - If you assign owner permissions to another user, your permissions automatically change to editor-level.



5. Use the search field to locate and select the user name or the **Everybody (Public)** option. This option grants view-only access to all users.

The user is now listed in the Who has access list. From this listing, you can change or delete the user's permissions.





6. Click the Apply button to save the user's permission level.

Removing a User's Access to a Data Collection

Only the data collection owner can remove a user's permissions.

- 1. Navigate to the Threat Library.
- 2. Load the data collection to which you want to remove a user's access.
- 3. Click the Share button.
- 4. Click the iii icon next to the user's name.



Deleting a Data Collection


To delete a data collection, you must have owner-level permissions for the data collection.



Deletion of a data collection cannot be undone. Exercise caution before deleting a data collection as it could be associated with integrations, custom dashboards, and other workflows in use with your organization.

Method 1:

- 1. Navigate to the Threat Library.
- 2. Click the **Load Data Collection Search** option.
- 3. Click the Owned By Me tab.
- 4. Check the box next to the data collection you want to delete.
- 5. Click the iii icon.
 The Delete Data Collection window prompts you to confirm your deletion
- 6. Check the warning checkbox and click the **Delete Data Collection** button to confirm.



Method 2:

- 1. Navigate to the Threat Library.
- 2. Load the data collection you want to delete.
- 3. Click the (1) icon next to the data collection name.
- 4. Click the iii icon.

 The Delete Data Collection window prompts you to confirm your deletion
- 5. Check the warning checkbox and click the **Delete Data Collection** button to confirm.



Exporting Search Results to CSV

You can export your search results as a CSV file, which allows you to use the data in another application, such as external spreadsheet software.




If you export a file with too many search results, the file may be too large to open in desktop applications. If you encounter this issue, you should separate your exports into smaller segments of data.



When exporting data collections to a CSV file, if you include additional columns beyond the default, this modification will impact the performance of the export process.

To export search results to a CSV file:

- 1. Navigate to the Threat Library.
- 2. Perform your search or load the appropriate data collection.
- 3. Click the **Actions** dropdown and select the **CSV** option under the *Export* heading.



The CSV file downloads to your desktop.





Bulk Actions

The Bulk Actions feature gives you the ability to update and delete large groups (1000+) of system objects from the Advanced Search page. Once selected, the job process will run in the background and allow you to continue working within ThreatQ. You can review the status of the job and its results on the Job Management page.




The fields listed in the **Bulk Actions Bulk Change form** may differ based on the type of system objects you have selected. **Example:** If you selected a set of events, the Change Expiration options will not be listed as expiration pertains to indicators only.

You will also receive in-app notifications, via the Notification Center, when a Bulk Action job has been queued and when it has been completed.

Upon initiating a Bulk Action, the job will be queued by the system and you will receive an inapp notification via the Notification Center icon. The system will also notify you, via the Notification Center, that the job has been completed.







You can also view the status and other details of the job on the Job Management page.




Bulk Add Source


Ű

If an object is already associated with the source selected for the Bulk Add Sources action, the object will be skipped during the bulk process.

1. Perform a search on the Threat Library.




2. Click on the **Actions** dropdown and select **All <System Object>** under the *Bulk Changes* heading.





You will see the number of system objects affected next to the link in parentheses.

The Bulk Changes form will load.



3. Click on Add Row under the Source heading.

A new row with a dropdown option will load.

Sources



4. Use the dropdown to select the source to add to the selected objects. You can also use the **Add New Source** link to add a source that is not listed in the dropdown.



If you have TLP enabled, you will also be able to update the designation for the source selected or keep the source-default designation.

Source

Source

Source

TLP

TLP

TLP

RED

AMBER


GREEN

WHITE

NONE


Bulk Add/Remove Attributes

1. Perform a search on the Threat Library.






2. Click on the **Actions** dropdown and select **All <System Object>** under the *Bulk Changes* heading.



You will see the number of system objects affected next to the link in parentheses.


The Bulk Changes form will load.





- Only the Bulk Actions that relate to the type of system object you selected will load on the Bulk Changes form.
- Bulk Expiration Change will not load for non-indicators.
- 3. Locate the Attributes heading and select either **Add** or **Remove**.
- 4. Select the attribute **Name** and **Value**. You can also use the **Add New Name** and **Add New Value** options to create new attributes. If you are adding an attribute, you will also select a **Source**. If you do not select a **Source**, the Source default will automatically be used.

Attributes





Click on **Add Row** and repeat steps 3-4 to add/remove multiple attributes. See the Scenarios section below for more details.

5. Click on **Apply Changes** located at the bottom of the form.

Bulk Add/Remove Attribute Scenarios

> Add Multiple Attributes

- 1. The user narrows down the Threat Library using advanced search filters.
- 2. The user selects **Bulk Changes** from the **Actions** dropdown.
- 3. The user enters the **Attribute Name**, **Value**, and **Source** for the first row in the *Attributes* section.
- 4. The user clicks on Add Row.
- 5. The user enters the **Attribute Name**, **Value**, and **Source** for the new row.
- 6. The user clicks on **Apply Changes**.



Results

· All objects with in the list will have those attributes added



The attributes will be listed in the audit log mentioning that this. The author of the action will be "Job ID <job_id_number> (<username>)"

> Remove Multiple Attributes

- 1. The user narrows down the Threat Library using advanced search filters.
- 2. The user selects **Bulk Changes** from the **Actions** dropdown.
- 3. The user selects **Remove** from the dropdown in the *Attributes* section and then enters the **Attribute Name**, **Value**, and **Source** for the first row.
- 4. The user clicks on Add Row.
- 5. The user selects **Remove** from the dropdown and then enters the **Attribute Name**, **Value**, and **Source** for the second row.
- 6. The user clicks on **Apply Changes**.

Results

 All objects in that change set that have the attributes specified (exact Name, Value, Source) will have them removed



The attributes will be listed in the audit log mentioning that this. The author of the action will be "Job ID <job_id_number> (<username>)"

Any object that does not have the attributes specified (exact Name, Value, Source)
 will be skipped.



There will be no mentions of the job in the audit log for those objects because no changes were made.

> Add and Remove Attributes


In this scenario, the platform will execute the Bulk Changes in the following order:

- 1. Add Attributes See the Add Multiple Attributes Scenario above.
- 2. Remove Attributes See the Remove Multiple Attributes Scenario above.




Bulk Add/Remove Tags

1. Perform a search on the Threat Library.




2. Click on the **Actions** dropdown and select **All <System Object>** under the *Bulk Changes* heading.



You will see the number of system objects affected next to the link in parentheses.




The Bulk Changes form will load.



3. Select whether either the **Add** or **Remove** function and the **Tag**. You can also use the **Add New Tag** option if the desired tag is not listed in the dropdown.





4. Click on **Apply Changes** located at the bottom of the form.




Bulk Change Expiration Date


Ű

This function can only be performed on Indicators.

1. Perform a search on the Threat Library.




2. Click on the **Actions** dropdown and select **All <System Object>** under the *Bulk Changes* heading.





You will see the number of system objects affected next to the link in parentheses.

The Bulk Changes form will load.



3. Select the type of expiration update to perform:

See the Bulk Change Expiration Date Scenarios topic for specific details and outcomes.

• Extend expiration date



The platform will ask you for the number of days to extend the expiration upon selection.

- $\,{}^{\circ}\,$ Protect from auto-expiration
- Remove expiration date
- Set a new expiration date



The platform will ask you to select a new date using a date picker upon selection.

4. Click on **Apply Changes** located at the bottom of the form.



Bulk Expiration Change Scenarios

> Expiration isn't part of the form if indicators are not part of the result set

- 1. The user attempts to make bulk expiration changes to system objects other than indicators.
- 2. The Change Expiration Date option will not be listed on the Bulk Changes form.

> Setting Expiration policy to a specific day

- 1. The user selects a set of indicators using the advanced search.
- 2. The user selects **Set a New Expiration Date** from the Change Expiration option.
- 3. The users selects a day using the date picker.



The date selected must be a future date.

4. After submitting the request, all indicators as part of that record set have the new expiration date.

> Extending the expiration policy by a number of days

- 1. The user selects a set of indicators using the advanced search.
- 2. The user selects **Extend Expiration Date** from the Change Expiration option.
- 3. The user enters the number of days to extend.
- 4. After submitting the request, all indicators in that record set will now have their expiration date extended by that number of days specified.

> Remove an expiration policy

- 1. The user selects a set of indicators using the advanced search.
- 2. The user selects **Remove Expiration Date** from the Change Expiration option.
- 3. After submitting the request, all indicators in that record set will no longer have an expiration date.

Protecting items from auto-expiration

- 1. The user selects a set of indicators using the advanced search.
- 2. The user selects **Protect from Auto-Expiration** from the Change Expiration option.



3. After submitting the request, all indicators in that record set will have the **protect from auto-expiration** expiration policy applied.

> Extending/Setting an expiration date of an indicator with a status of Expired

- 1. The user selects a set of expired indicators using the advanced search.
- 2. The user selects **Set a New Expiration Date** from the Change Expiration option.
- 3. The users selects a day using the date picker.



The date selected must be a future date.

4. After submitting the request, the expired indicators in that record set are then changed to a status of Active and the expiration date is set to the date indicated with the date picker.

> Extending/Setting an expiration date of an indicator with a status of Whitelisted

All whitelisted indicators included in a Expiration Change set will be skipped.

Removing an expiration date on a previously expired indicator

- 1. The user selects a set of expired indicators using the advanced search.
- 2. The user selects **Remove Expiration Date** from the Change Expiration option.
- 3. The expired indicators in the set are skipped.

Bulk Delete

The Bulk Delete feature offers users with Maintenance and Administrative roles the ability to select and delete system objects of all types, excluding Files and Tasks, from the Advanced Search page. In addition to the system object, bulk delete will also delete all child records such as attributes and relationships.



Individual Tasks and Files can be deleted by accessing the object's details page and selecting Delete Task/File from the Actions menu.

Once selected, the job process will run in the background and allow you to continue working within ThreatQ. An in-app notification will alert you when a Bulk Delete job has been queued and when it has been completed. You can also view the status and outcome of the job from the Job Management page.




A

The Bulk Delete function **permanently** deletes selected indicators from the system. Once deleted, you will be unable to undo the action. If you are executing a Bulk Delete on a large group of indicators, ThreatQuotient highly recommends performing a backup of your system before performing this function.

A


Based on the size of your bulk delete job and the system resources available, you may find that the estimated job duration is quite long. In these rare instances, contact ThreatQ support to explore your other options for deleting a large number of objects.

1. Perform a search on the Threat Library.






2. Click on the **Actions** dropdown and select **All <System Object>** under the *Bulk Delete* heading.



ď

You will see the number of system objects affected next to the link in parentheses.

The Bulk Action Confirmation dialog box will load.



3. Click on the checkbox to confirm deletion and then click on **Delete**.




Bulk Add/Remove Relationships

You can use the Bulk Change option to add/remove relationships for a group of objects, per object type, on the Advanced Search page.




If an object is already associated with the source selected for the Bulk Add Relationships action, the object will be skipped during the bulk process.

1. Perform a search on the Threat Library.






2. Click on the **Actions** dropdown and select **All <System Object>** under the *Bulk Changes* heading.



You will see the number of system objects affected next to the link in parentheses.

The Bulk Changes form will load.








Only the Bulk Actions that relate to the type of system object you selected will load on the Bulk Changes form. **Example:** Bulk Expiration Change will not load for non-indicators.

3. Locate the Relationships heading and optionally select **Limit Search To** to select an object type.



4. Enter an object name.



By default, this field searches for objects that begin with the search string you enter. To search for objects that include your search string but do not begin with it, you must use a wildcard (% OR *) search.

Examples:

- 1. When you enter "us", your search returns **US**Bferry and **US**BStealer.
- 2. When you enter "%us" or "*us", your search returns Aquarius, Lazarus Group, Dust Storm, USBferry, and USBStealer.
- 5. After you select an object, the Add/Remove option appears.



- 4. Select either Add or Remove.
- 5. Use the dropdown to select the source to add to the selected objects. You can also use the **Add New Source** link to add a source that is not listed in the dropdown.
- 6. Click on **Apply Changes** located at the bottom of the form.




Bulk Status Change

Ű

This function can only be performed on objects that use the status field such as Indicators, Signatures, etc.


Whitelisted Indicators are not affected by Bulk Status Change. If a Whitelisted Indicator is included in the set of system objects selected for a Bulk Status Change, the platform will skip the object without making a status change.

1. Perform a search on the Threat Library.






2. Click on the **Actions** dropdown and select **All <System Object>** under the *Bulk Changes* heading.



You will see the number of system objects affected next to the link in parentheses.

The Bulk Changes form will load.






- 3. Use the dropdown provided to select a new status to be applied to the selected objects.
- 4. Click on **Apply Changes** located at the bottom of the form.



Object Details

You can click on an object within the ThreatQ application to access its details page. The Object Details page provides you with an in-depth look at an individual object. You can enter comments for others to view, link related objects, and view an audit log of all activity associated with the object.

Specific objects, such as Indicators, will display additional information such as the indicator's status, score, and expiration data.





Items marked with an * in the Object Details Legend indicate an option only available to specific object types.

OBJECT DETAILS PAGE LEGEND

Head	1~-	C_{α}	-+:	
пеао	er.	76	(OII

riedaer Section			
Number	Field	Description	Reference
1	Edit Object Link	The Edit link allows you to edit specific details about an object. Edit fields will differ based on the type of object.	N/A
2	Score Selection* Applies to Indicator Object Types Only	The Score Selection dropdown allows you to override an indicator's score set by the scoring algorithm.	Indicator ExpirationScoring Algorithms
3	Scoring Influence* Applies to Indicator Object Types Only	You can click on the icon to review the criteria utilized by the application's scoring algorithm to generate the Indicator's score.	• Scoring Algorithms
4	Status* Applies to Indicator Object Types Only	The Status dropdown menu allows you to manually set the status of an indicator. Default statuses include: Active, Expired, Indirect, Review, and Whitelisted.	 Indicator Status Indicator Statuses Management (Object Management)
5	Add to Watchlist	The Watchlist toggle button allows you to add and remove	 Add/Remove an Object to the Watchlist



		OBJECT DETAILS PAGE LEGEND	
		the object from the Watchlist widget.	
6	Expiration* Applies to Indicator Object Types Only	The Expire link allows you to set an expiration date for the indicator, protect from auto- expiration policies, and remove an existing set expiration date.	 Indicator Expiration Indicator Expiration (Data Controls)
7	Touched At	The Touched At field displays the date and time any item associated with the object, such as an attribute, source, or relationship, was last changed.	• Date and Time Stamps
Details Sec	ction		
Number	Pane	Description	Reference
8	Attributes	The Attributes pane displays attributes associated with the object. You can Add, Edit, and Delete attributes found in this section.	• Attributes Pane
9	Sources	The Sources pane displays sources associated with the object. You can Add additional sources to an object.	• Sources Pane
10	Tags	The Tags pane displays tags associated with the object. You can Add and Delete tags found	• Tags Pane

in this section.



		OBJECT DETAILS PAGE LEGEND	
11	Description	The Description pane allows you to add general information about the object.	• Description Pane
12	Adversaries	The Adversaries pane displays adversaries associated with the object.	• Relationships Panes
13	Files	The Files pane displays files associated with the object.	• Relationships Panes
14	Indicators	The Indicators pane displays indicators associated with the object.	• Relationships Panes
15	Tasks	The Tasks pane displays tasks associated with the object.	• Relationships Panes
16	Comments	The Comments pane allows you to record comments about the object for other users to read and reference.	• Relationships Panes
17	Operations	The Operations pane allows you to associate third-party	 Integrations Management

attributes and related indicators

Note: This options requires the installation of Operations. See the Managing Integrations topic

to the indicator.

for more details.



OBJECT DETAILS PAGE LEGEND

18 Audit Log The Audit Log panel displays all actions and changes made to an Object.

• Audit Log


Left-Hand Navigation

Number	Field	Description	Reference
19	Actions Menu	The Actions menu lists the following option: • Add Attribute • Add Comment • Add Relationship • Add Source • Create Task • Generate PDF • Delete Indicator	• Actions Menu
20	Details Navigation Tabs	This allows you to jump to a particular pane on the Object Details page.	N/A



Adding/Removing an Object to the Watchlist

- The steps to remove an item from the Watchlist are the same as adding an item.
- 1. From the ThreatQ user interface, navigate to the Details page of system object you want to track.
- 2. Click **Add to Watchlist** to track that item.




The object will be added to the Watchlist on the system default dashboard.



Actions Menu

The Action Menu, located on the left-hand of the Object Details page, allows users to quickly execute system object processes.



Actions Include:

ACTION	FUNCTION	REFERENCE
Add Attribute	Brings up the Add Details dialog box to add an attribute to the object.	• Attributes Pane
Add Comment	Creates a new text box entry in the comment pane.	Comments Pane



ACTION	FUNCTION	REFERENCE
Add Relationship	Brings up the Add Relationships dialog box to link other system objects to the object.	Relationships PanesAdditional Related Object Actions
Add Source	Brings up the Add Details dialog box to add a source to the object.	• Sources Pane
Create Task	Opens up the Add Task dialog box.	• Tags Pane
Generate PDF	Generates a PDF report of the object.	• Reports
Delete < <i>Object</i> >	Deletes the system object.	N/A



Context Panes

The Context section of the object details page displays attributes, sources, and tags associated with the system object.



Attributes Pane

The Context section of the object details page displays attributes, sources, and tags associated with the system object.




Adding an Attribute to an Object

You can link adversaries to a system object.

- 1. Locate the Attributes pane on the object details page.
- 2. Click on the **+ Add Details** link located to the top-right.

 The Add Details dialog box opens with the Add Attributes tab selected by default.



- 3. Select an **Attribute Type** from the Attributes dropdown or enter a new type.
- 4. Select an existing **Attribute Value** from the dropdown or enter a new value.
- 5. Select a **Source** from the dropdown or enter a new source.



6. Select Add Attributes.



Deleting an Attribute from an Object

You can delete an attribute from the object details page.

- 1. Locate the Attributes pane on the object details page.
- 2. Select the checkbox next to the attribute to delete.
 - 🎒 You can select more than one attribute to delete
- 3. Select **Delete**.

The confirmation dialog box opens.



4. Select Delete Attributes.

Deleting an Attribute Source from an Object

You can delete an attribute's source from the object details page.

1. Locate the Attributes pane on the object details page.



2. Select the **X** next to the attribute's source. The confirmation dialog box opens.



3. Select Delete Attribute Source.

ml>l>



Sources Pane


The Sources pane displays all sources associated with the system object.

See *Bulk Add Source* section in the *Bulk Actions* topic for information on adding a source to a group of system objects.

Adding a Source to an Object

You can add sources to a system object in its details pane.

- 1. Locate the Sources pane on the object details page.
- Click on the + Add link located to the top-right.
 The Add Details dialog box opens with the Add Source tab selected by default.



- 3. Select a **Source** from the dropdown provided. If TLP is enabled, you can override the source-default TLP designation.
 - You can also click on **Add a New Source** if the desired source is not listed in the dropdown list. If administrators have enabled TLP view settings, users can select a TLP designation light for the new source in the dropdown list provided. See the Traffic Light Protocol (TLP) topic for more information on TLP schema.





4. Select **Add Sources**.



Tags Pane

You can add and remove tags in the Tags pane on the object details page.

See Bulk Actions Add/Remove Tags for information on adding/removing tags from a group of system objects.

Adding a Tag to an Object

- 1. Locate the Tags pane on the object details page.
- 2. Select the Tags text field and enter the tag.
- 3. Press [Enter] or [Return].



Repeat steps 2-3 to add additional tags.

Deleting a Tag from an Object

- 1. Locate the Details pane on the object details page.
- 2. Select the **X** next to the tag to delete.



Description Pane

The Description Pane section of the object details page allows you to add a description for the system object.

Updating the Description of an Object

- 1. Locate the Description pane on the object details page.
- 2. Select Edit.
- 3. Make the required changes and select **Save**.



Relationships Panes

The Relationship section of the object details page displays other system objects that have been related to the current object.

You can link/unlink system objects from relationship panes and perform bulk updates (related indicators pane only). You can click on a related object to navigate to its object details page.



Certain related system objects, such as related indicators, will have additional actions available. See the Additional Related Object Actions topic.

Linking a System Object

1. Locate the desired system object type pane on the object details page.



Relationships panes will only appear if a system object is already related to the object. Use the **Actions** button to relate the initial object: **Actions > Add Relationship**.

2. Select the & Link icon.

The Add Relationships dialog box opens.



- 3. Use one of the following methods to add an object to the Add Relationships field:
 - For existing objects, enter the object name and select the match from the down list.



Repeat this step to add multiple objects.



- To create a new object, enter the new object name. The, click the Create link to add the new object to Threat Library. If you limited your search to a specific object type, you are linked to the corresponding form. For example, if you limited your search to Adversaries, the Create link opens the Add An Adversary form. If you left the Limit search to field set to All Objects, you can select the object type you want to create from a drop-down list.
- 4. Click Add.

Unlinking a System Object

- 1. Locate the Related <System Object> pane on the object's details page.
- 2. Select the checkbox(es) next to the system objects to unlink.
- 3. Select the & Unlink icon.



Additional Related Object Actions

Certain system object types will offer you additional actions after relating the objects to another object.

Adding a comment to a related adversary

- 1. Locate the Adversaries pane on the object details page.
- Select Add a Comment.The Comments text field opens.



- 3. Enter a comment.
- 4. Click Add Comment.

Editing a related adversary comment

- 1. Locate the Related Adversaries pane on the object details page.
- 2. Select **Edit** under the comment to update.
- 3. Update the comment.
- 4. Click Save Changes.

Deleting a related adversary comment

1. Locate the Related Adversaries pane on the object details page.



2. Select **Delete** under the comment to update. A confirmation dialog box opens.




3. Select Delete Comment.

Related Adversaries - Confidence Level

You can configure a related adversary's confidence level from the Adversaries pane.

- 1. Locate the Adversaries pane on the object details page.
- 2. Click the dropdown arrow to the right of the adversary, and slide the scale to the desired confidence level.





The confidence level can be set to 0, 25, 50, 75, and 100.


The displayed confidence level will be modified to reflect your selection.



Related Indicators - Bulk Actions

You can perform bulk updates to linked indicators listed in the Indicators pane of an object.

- 1. Locate the Indicators pane on the object details page.
- 2. Select the checkbox(es) next to the indicator(s) to update.
- Select the Bulk Update icon.
 The Bulk Update form loads.



4. Select the desired changes and click **Apply Changes**.



Comments Pane

The Comments pane allows users to record comments about the system object for other users to see.

Adding Comments to an Object



Users can also click on the **Actions** menu and select the **Comment** option.

- 1. Click on the expand icon 🗈 to expand the Comments pane.
- 2. Click on the Add link located at the top-right of the pane.

The new comment text box opens.



- 3. Enter a comment.
- 4. Click on the Add Comment button.

Editing Comments for an Object

- 1. Click on the expand icon \blacksquare to expand the Comments pane.
- 2. Click on the **Edit** link located beneath the comment to update.



The edit comment text box opens.




- 3. Edit the comment.
- 4. Click on the Save Changes button.

Deleting Comments from an Objects

- 1. Click on the expand icon \blacksquare to expand the Comments pane.
- 2. Click on the **Delete** link located beneath the comment to update..

The delete confirmation dialog text box opens.



3. Click on the **Delete Comment** button.



Audit Log

The ThreatQ Audit Log tracks every change made to every object in the system. If there is a change to an object, that change is displayed in the audit log. The audit log is only updated if the data itself changes, not just the updated_at value.

The following questions below address further details about the audit logging process.

In the case where an activity is triggered (with nothing updated), where will the activity be logged?

The activity will not show in the audit log, as there were no changes to report. While ThreatQ does not track duplicate objects that enter the application, there is a touched_at date field on primary objects (Adversaries, Files, Events, Indicators, and Signatures) that indicates when a relation of the object has been changed.

Is there another raw audit log within the system where events are logged? No, there are no other raw audit logs where events are logged.

Is there an option in the User Interface to enable all activities to be shown in the Audit Log? There is no option in the User Interface to limit or expand the audit log. All entries are pulled for an object when the Audit Log panel is opened. The audit log displays changes to the individual fields of an object; object comments, sources, attributes, and tags; as well as to object links, object link comments, and object link attributes. Additionally, any changes to the score of an Indicator are included.



Troubleshooting

The following topics provide basic troubleshooting steps and platform information.

- Generating a Troubleshooting Package
- SSL Certificates
- ThreatQ Critical System Processes
- Date and Time Stamps



Generating a Troubleshooting Package

In the event that ThreatQ Support requests a troubleshooting package, this topic explains how to create the package. This is a command line tool for gathering all the useful information for troubleshooting issues on a ThreatQ host.

- 1. Access the ThreatQ host command line via SSH or console.
- 2. Change directories:

```
<> cd /var/www/api/
```

3. Run the following command:

```
<> sudo php artisan threatq:get-debug-info
```

The command for getting hardware info (hwinfo) may not be installed. In this case, an error message is shown, but the execution is not affected.

You may get a tar notification about the laravel.log file being modified as it is read, this does not affect the process outcome.

The process creates a file named debug_info.tar.zip in /var/tmp/.

4. Send the file to ThreatQ Support and remove it from the host to conserve disk space.



SSL Certificates

ThreatQ performs SSL certification validation on outgoing connections. At times, an incoming feed (particularly TAXII feeds) or operation may require access to sites with CA certificates that are not included in the default bundle included in the software packages ThreatQ uses by default. These certificates will need to be added to the ThreatQ server for these connections to pass validation.

Unable to Verify SSL Certificate

If you find that a feed or operation is not working and results in an "unable to verify SSL certificate" error, complete the following steps:

1. Obtain the remote site's CA in PEM format and upload it to the ThreatQ filesystem:

```
<> /etc/pki/ca-trust/source/anchors/
```

2. Enable it in the system with the command:

```
<> sudo update-ca-trust extract
```

3. Restart the feed ingestion engine:

```
<> sudo systemctl restart threatq-dynamo
```

Contact ThreatQ Support for assistance with obtaining or installing needed CA certs, or if you experience problems with SSL connections.

Configuring Custom SSL Certificates (not self-signed)

You may wish to install your own custom SSL certs to ThreatQ. This can be done according to the standard CentOS Linux instructions, which are included below:

1. Create the following directory if it does not currently exist:

```
<> mkdir /etc/httpd/ssl
```

2. Copy your .crt and .key files to the ThreatQ file system, into the SSL directory, and then restrict the permissions:



- 3. SSH to your server and edit the ssl.conf file:
 - <> sudo vi /etc/httpd/conf.d/ssl.conf
- 4. Comment the following lines with a # if they exist:
 - <> #SSLCertificateFile /etc/pki/tls/certs/localhost.crt
 #SSLCertificateKeyFile /etc/pki/tls/private/localhost.key
- 5. Add the following lines as appropriate
 - <> SSLCertificateFile /etc/httpd/ssl/yourcert.crt
 SSLCertificateKeyFile /etc/httpd/ssl/yourkey.key
 SSLCertificateChainFile /etc/httpd/ssl/yourca.crt (if a
 certificate chain is required)
- 6. Save the file.
- 7. Restart Apache:
 - <> sudo systemctl restart httpd



ThreatQ Critical System Processes

The table below contains a list of critical ThreatQ processes and how they are utilized by the ThreatQ platform.

PROCESS	DESCRIPTION
threatq-containers / docker.service	The threatq-containers houses three processes: • memcache • websocket • rabbitmq* *rabbitmq is used to queue worker jobs and general system messaging such as sending configuration updates, received from the API, to dynamo. In ThreatQ instances prior to 4.39.0, rabbitmq is used for legacy feed data ingestion.
httpd.service	httpd.service is the Apache web host service for the ThreatQ user interface (UI) and API.
mariadb.service	The mariadb database, which functions as the ThreatQ data persistence service.
solr.service	Solr is an open-source enterprise search platform that is used as the primary index for the ThreatQ user interface (UI).
threatq- dynamo.service	ThreatQ-dynamo is the process that handles CDF feed runs and the processing of data returned by feed providers.
threatq- feeds.service	The threatq-feeds.service is utilized by ThreatQ instances prior to version 4.39.0 The service controls the feed scheduling and data processing of legacy feed data from feed providers.



PROCESS DESCRIPTION threatq-jobs.target Threatq-jobs.target manages the ThreatQ worker processes that handle Bulk Update actions such as Bulk Delete and Bulk Update.



Date and Time Stamps in ThreatQ

ThreatQ provides date and time stamps for threat intelligence, so that you can track the flow of data in the platform. The following table provides an overview of what these various stamps indicate in the ThreatQ platform.

ThreatQ UI Date and Time Stamps

DATE AND TIME STAMP	DEFINITION
(Date) Created	This indicates the date when the object was added to ThreatQ.
Due Date	The due date set by the user for a task. See the Tasks topic for more details.
Expiration Date	This is the expiration date for a system object. See the Indicator Expiration and Automatic Expiration topics for more details.
First Published	 Varies, depending on the object source: If the source doesn't contain a publication date, this date indicates the first time the object is imported into ThreatQ. In this case, the created and first published dates will match. If the source contains a publication date, this date indicates the first time the object was published by the feed.
Last Modified	The date and time when object-specific information was last updated, such as updating an indicator's status.



Time

DATE AND TIME STAMP Adding/editing/removing associated information, such as attributes, sources, and relationships, does not update the Last Modified time stamp. Touched At The date and time any item associated with the object, such as an attribute, source, or relationship, was last changed. Source Ingest The date and time that an object was initially reported by a source.



User Management

ThreatQ uses role-based access control to manage user accounts. The system provides several user roles, each containing a set of permissions for accessing system functionality. You create user accounts, and assign them to a user role. The user role determines each account's set of permissions.

After you create a user account, you can modify the user role group, full name, and email address.



Managing User Accounts

While all users can update their own individual accounts, only users with Maintenance Account and Administrative Access user roles have permission to access the User Management functionality. You must be logged in as of these roles in order to create new user accounts.



When you first install ThreatQ, the system creates a default user account, the Maintenance Account. You cannot delete this account. You can use it to initially create other user accounts. Each user account must have a unique username.

Accessing Your User Account

1. Click on your avatar icon, located to the top-right of the platform, and select **My Account**. The Edit User screen allows you to review and update your User Account Properties.

Accessing Other User Accounts



Only users with Maintenance and Administrative accounts can add, edit, and delete other user accounts.

- 1. Click on the **Settings** icon and select **User Management**. The User Management screen displays a list of user accounts.
- 2. You can filter and/or sort the the user accounts displayed by:
 - Display Name
 - Status
 - Username
 - Email
 - Group
 - · 2-Step Verification
- 3. If you are logged in with a Maintenance or Administrative account, you can also click a display name to access the corresponding User Account Properties.



User Account Properties

FIELD	DESCRIPTION
Name	Update the user's name.
Title	Update the user's job title.
Email	You can update the user's email address.
Password	You can click on the Change Password link to update the user's password.
API Credentials	You can view the user's API credentials, a unique Client ID, which will allow him/her to connect with ThreatQ's API.
Session Timeout	You can update or disable the user's session timeouts.
User Avatar	You can update the user avatar graphic.
2-Step Verification	Optionally, you can enable/disable 2-step verification; see 2-Step Verification for more details.
Activity Log	 You can click on the Activity log tab to view the following information: The last date and time the user logged in. The IP Address where the user logged in. Whether the login was successful or not.



Adding a User



Only users with Maintenance and Administrative accounts can add user accounts.

- 1. From the main menu, choose the **Settings icon** > **User Management**.
- 2. Click Add User.
- 3. Enter the user's Name.
- 4. Optionally, enter the user's **Title**.
- 5. Select the level of access for the user from the **Group** drop-down menu.

Choose from the following options:

- Maintenance Account
- Administrative Access
- Primary Contributor Access
- Read Only Access
- 6. Enter the user's **Email** address.
- 7. Enter a password for the user.
- 8. Retype the password.
- 9. Click Add User.

Editing a User



Only users with Maintenance and Administrative accounts can add user accounts.

You cannot edit user details for SAML nor LDAP users from the User Management page.

1. Click on the **Settings** icon and select **User Management**.




To edit your own account, click on your avatar icon and select My Account. Proceed to step 3 below.

2. Click the name of the user whose profile you wish to edit.



The User Profile page loads.



3. On the User Profile tab, you can view and/or edit the following settings:


FIELD	DESCRIPTION

Name	Update the user's name.
Title	Update the user's job title.
Email	You can update the user's email address.
Password	You can click on the Change Password link to update the user's password.
API Credentials	You can view the user's API credentials, a unique Client ID, which will allow him/her to connect with ThreatQ's API.
Session Timeout	You can update or disable the user's session timeouts.



User Avatar	You can update the user avatar graphic.
2-Step Verification	Optionally, you can disable 2-step verification; see 2-Step Verification for more details.

- 4. Optionally, you can click on the Login Activity tab to view:
 - The last date and time the user logged in.
 - The IP Address where the user logged in.
 - Whether the login was successful or not.



5. Click Save.

Resetting User Password from the Command Line

If you have root access to your ThreatQ installation, you can reset any user's password from the command line. See the commands and instructions in the Resetting User Passwords from the Command Line entry in the Command Line section of this guide.

Deleting a User



Deleting a user cannot be undone.

- 1. From the main menu, choose the **Settings icon > User Management**.
- 2. Select the user(s) you wish to delete.
- 3. Click the Delete icon.

 If the user has any shared data collections or dashboards, you must reassign owner



Are you sure?

Tech Pubs has shared data collections or dashboards. How would you like to proceed?

Reassign to user

By checking this box, it confirms you are deleting this user. This cannot be undone.

5. Check the confirmation checkbox and click the **Delete User** button.

Updating User Avatar

User avatar icons provide a personalized look to your ThreatQ dashboard. Clicking on the avatar icon will reveal the **My Account** and **Log out** options.

You can update your avatar by clicking on the avatar icon and selecting My Account.

1. Click on avatar icon located to the top-right on the screen and select My Account.

The Edit User form will load.

- 2. Select one of two options:
 - Click browse and select the icon graphic to upload.
 - Click and drag the new icon graphic onto the page.
- 3. Click **Save** at the bottom of the page.



User Roles

The following details the user roles and their base-level permissions. A user account's access to data collections and dashboards can be further customized by the Sharing permissions assigned to it.

LICED	ROLE	
II/FR	RUIF	

PERMISSION

Maintenance Account

Members have access to the entire ThreatQ user interface and can edit all data.

Important Notes:

- The initial local Maintenance Account, created when installing ThreatQ, cannot be deleted
- Local Maintenance Accounts (manually created within ThreatQ) cannot be migrated to SAML authentication groups

Administrative Access

Members have access to the entire ThreatQ user interface and can edit all data.

Primary Contributor Access

Members can:

- · Edit their own user info
- · Manually create system objects
- Create and manage ThreatQ Investigations
- Access Whitelist Management (Data Controls)
- Perform a basic search
- Access the Threat Library, object metadata, export search results, and manage Data Collections
- Create custom dashboards and add shared dashboards to their user view.



Read Only Access

Members can:

- Access the Threat Library, object metadatal, export search results
- Add shared dashboards to their user view
- Load saved Data Collections



Members cannot edit any data.



LDAP Authentication



AGDS Users -If you are using LDAP or SAML authentication on your **Source** ThreatQ instance, and require users transferred via import to have authentication capabilities on your **Target** ThreatQ instance, then you must enable the same authentication method on your **Target** ThreatQ instance prior to performing import.

ThreatQ allows you to configure system access via LDAP, the Lightweight Directory Access Protocol. You have two configuration options:

- Anonymous Bind (previously referred to as basic)
- Authenticated Bind



It is highly recommended that you review the Required Information for Creating LDAP Authentication section of the LDAP Authentication topic before configuring your LDAP settings.

To Access the LDAP tab:

- 1. From the main menu, select the Settings icon > User Management.
- 2. Click the LDAP tab.



The LDAP tab opens with the Legacy LDAP form loaded by default. THREATQ 🍮 M. Threat Library User Management System Users LDAP SAMIL Lightweight Directory Access Protocol (LDAP) is a lightweight client-server protocol for accessing directory services and is used for authentication and storing information. Complete the fields below to set the primary server settings and map your permission levels to LDAP Legacy LDAP Settings Updated LDAP Settings **Primary Server Settings** Map Your Permission Levels to LDAP (Note: You cannot list the same LDAP User Group for Multiple permission levels) Server Address Port # This should be the CN value of your LDAP Query. Administrative Access LDAP Domain Primary Contributor Access LDAP Group Domain Read Only Access Append Domain to Username?

Required Information for Creating LDAP Authentication

Before you configure a connection to your LDAP server, you should work with your LDAP administrator to collect, at minimum, the following information:

Anonymous Bind

- LDAP Server URL
- LDAP Port
- LDAP Group Field Name
- · LDAP Filter Field Name
- · LDAP group mappings for super, maintenance, analyst, and observer

Authenticated Bind

- LDAP Server name or IP Address
- LDAP port



- LDAP base DN
- LDAP Group Member Field Name
- LDAP Primary Group Name
- Whether to use LDAP over SSL (Idaps or Idap)
- LDAP User Id Key Field Name
- LDAP User Group Member Key Field Name
- LDAP group mappings for super, maintenance, analyst, and observer

Switching LDAP Connections

To switch between using the Anonymous (Legacy) and Authenticated (Updated) Bind LDAP connections, open the desired connection type's form in the LDAP section and click on the Save button.



Example: A User is using the legacy LDAP Settings option. He switches to the Updated LDAP tab and clicks on Save. ThreatQ will now use the Updated LDAP Settings. If he switches back to the Legacy LDAP tab and clicks on Save again, ThreatQ will start using the Legacy LDAP settings again.



Anonymous Bind




Only users with an Administrative or Maintenance account can access LDAP settings.



 $oldsymbol{lack}$ ThreatQuotient strongly recommends that you perform a full backup before changing your authentication method.

- 1. Navigate to Settings > User Management.
- 2. Click on the LDAP option.

The Legacy LDAP Settings form will load by default.



3. Complete the following server settings:

FIELD

DESCRIPTION

Server Address

Enter the name of the server where LDAP is hosted.

Example: Idap://[servername]



FIELD	DESCRIPTION
Port #	389 for LDAP 636 for LDAPS If LDAPS is used, the Port # will default to 636.
LDAP Domain	Enter the domain for which LDAP is configured to authenticate. Example: threatq.com
Append Domain to Username	Choose from the following options: • Yes for most Active Directory servers • No for most Open LDAP servers
Filter Field Name	This field is specific to your LDAP directory configuration. AD Example: memberuid OpenLDAP Example: uid
Group Field Name	This field is specific to your LDAP directory configuration. AD Example: memberof OpenLDAP Example: cn



FIELD	DESCRIPTION
Use RDN?	Choose from the following options: • Yes to use Relative Distinguished Names. • No to use full Distinguished Names
Organizational Unit (OU)	This field is specific to your LDAP directory configuration. Your LDAP administrator should provide the correct value for this field.
User Lookup Name	This field is specific to your LDAP directory configuration. AD Example: memberUid OpenLDAP Example: uid

4. Complete the MAP your Permission Levels to LDAP section:



You can not list the same LDAP User Group for multiple permission levels. For roles not mapped, you should enter a hyphen: "-." You cannot save the configuration without entering a value in each field.

FIELD	EXAMPLE
Maintenance Account	OpenLDAP Example: IdapSuper
	AD Example: CN=tq ₋ maintenance,CN=Builtin,DC=yourdomain,DC=com



FIELD EXAMPLE

Administrative

Access

OpenLDAP Example: administrator

AD Example:

CN=linux_admins,CN=Builtin,DC=yourdomain,DC=com

Read Only Access OpenLDAP Example: IdapObserver

AD Example:

CN=read_onlyCN=Builtin,DC=yourdomain,DC=com

Primary Contributor Access OpenLDAP Example: IdapAnalyst

AD Example:

CN=primary_contributor,CN=Builtin,DC=yourdomain,DC=com

- 5. Click Save.
- 6. Click on the Enable/Disable toggle switch to enable LDAP.



If your LDAP fails to enable or fails to function properly, validate your inputs. If the configuration continues to fail, please contact ThreatQ Support.

Configuring Secure LDAP

The following instructions are for Anonymous Bind LDAP connections only. The steps needed to create a secured connection authenticated bind are included in the Configuring Authenticated Bind LDAP Settings topic.

ThreatQuotient strongly recommends that you perform a full backup before changing your authentication method.



To configure secure LDAP, you must complete the following steps:

- 1. Enter your LDAP settings in the ThreatQ user interface. See the Anonymous Bind steps above for more details.
- 2. Access the ThreatQ appliance command line as root and edit and navigate to the following directory: /etc/openIdap/.
- 3. Use vi to edit ldap.conf and update/confirm that your settings are as follows:

```
# LDAP Defaults
# See ldap.conf(5) for details
# This file should be world readable but not world writable.
       dc=[your domain],dc=com
URI ldap://[your servername]:389 ldaps://[your servername]:636
#SIZELIMIT 12
#TIMELIMIT 15
#DEREF
        never
TLS_CACERTDIR /etc/openldap/certs
# Turning this off breaks GSSAPI used with krb5 when rdns = false
SASL_NOCANON
TLS_REQCERT allow
```



🛕 ThreatQ recommends that you edit ldap.conf on the appliance, rather than editing off box and uploading it. If you do edit the file off box, ensure that you use a linux editor. Windows and Mac editors may corrupt the file.



If your LDAP fails to enable or fails to function properly, validate your inputs. If the configuration continues to fail, please contact ThreatQ Support.




Authenticated Bind



It is recommended that you contact ThreatQ Support before configuring an authenticated bind connection.

- ď
- Only users with an Administrative or Maintenance account can access LDAP settings.
- 1. Navigate to Settings > User Management.
- 2. Click on the LDAP option and select the Updated LDAP Settings tab.

The Updated LDAP Settings form will load.



3. Complete the **Server Connections Settings** section:

FIELD DESCRIPTION

Account Suffix The LDAP account suffix.



FIELD	DESCRIPTION
Host Address	Name of the LDAP domain controller without the protocol. Example: tqldap.threatq.com
Port Number	The LDAP port; either 636 or 389 . Only standard ports for secured and unsecured connections are supported. Use port 636 if using SSL to create a secured connection.
Admin Username	The LDAP administrative username.
Admin Password	The LDAP administrative password.
Click on Tost Connections to varify the settings are correct	

- 4. Click on **Test Connections** to verify the settings are correct.
- 5. Complete the **LDAP Schema** section:

FIELD	DESCRIPTION
Base DN	The Base DN of the LDAP server connection.
	Example: DC=[server], DC="com"



FIELD	DESCRIPTION
DN Field Name	The field used to retrieve the DN or users and groups. This field should be DN for both OpenLDAP and Active Directory.
User Search Filter	The field to search for users. For OpenLDAP : objectClass=poslxAccount For Active Directory : objectClass=user
Group Search Filter	The field to search for grpups. For OpenLDAP : objectClass=poslxGroup For Active Directory : objectClass=group
Primary Group Name	The primary group name.
Group Member Field Name	This field is used to search for groups that a user belongs to. For OpenLDAP: cn For Active Directory: memberof



FIELD	DESCRIPTION
User ID Key Field Name	Field used to search for users based on email. For OpenLDAP : uid For Active Directory : sAMAccountName
User Group Member Key Field Name	Field used to search for groups that user belongs to. For OpenLDAP : memberUid For Active Directory : uid

6. Under the Protocols section, use the **Yes/No** toggle switch to select whether the connection will use SSL.

If the connection will use SSL, confirm that the port number, set in step 3, is 636 to create a secured connection.

7. Complete the MAP your Permission Levels to LDAP section:

You cannot use the same LDAP User Group for multiple permission levels. For roles not mapped, you should enter a hyphen: "-." You cannot save the configuration without entering a value in each field.

FIELD	DESCRIPTION
Maintenance Account	The LDAP account the ThreatQ Maintenance group will map to for permissions.
	Open LDAP Example: IdapSuper



FIELD DESCRIPTION

AD Example:

CN=tq_maintenance,CN=Builtin,DC=yourdomain,DC=com

Administrative Access The LDAP account the ThreatQ Administrative group will map

to for permissions.

Open LDAP Example: administrator

AD Example:

CN=linux_admins,CN=Builtin,DC=yourdomain,DC=com

Primary Contributor Access The LDAP account the ThreatQ Primary Contributor group will

map to for permissions.

Open LDAP Example: IdapAnalyst

AD Example:

CN=linux_admins,CN=Builtin,DC=yourdomain,DC=com

Read-Only Access

The LDAP account the ThreatQ Read-Only group will map to for

permissions.

Open LDAP Example: IdapObserver

AD Example:

CN=read_onlyCN=Builtin,DC=yourdomain,DC=com

- 8. Use the **Connect to Receive Data** section connect to your LDAP using the settings on this page to pull group information and user lists
- 9. Click Save.
- 10. Click the Enable/Disable toggle switch to enable LDAP.





Green indicates the feature is active.



SAML Authentication

Security Assertion Markup Language (SAML) is a single sign-on (SSO) standard that allows you to log into your ThreatQ instance using a credentials service outside of the platform.

Email addresses and passwords are authenticated outside of ThreatQ and user roles are determine using the permissions mappings located on the ThreatQ SAML configuration page.

Upon enabling SAML, users will see a SSO login option on the ThreatQ login page - see the Accessing the Platform topic.



Users cannot use SSO to log into a ThreatQ Local Maintenance account.



AGDS Users -If you are using LDAP or SAML authentication on your **Source** ThreatQ instance, and require users transferred via import to have authentication capabilities on your **Target** ThreatQ instance, then you must enable the same authentication method on your **Target** ThreatQ instance prior to performing import.

Configuring SAML




ThreatQuotient strongly recommends that you perform a full backup before changing your authentication method.



SAML users are required to add their email address to their user profiles in order to use the SSO. As part of the integration process, the ThreatQ platform expects that the user's email address has already been added to their IdP. See the Setting Up LDAP






LDAP must be disabled before enabling SAML. The ThreatQ platform will alert you if LDAP is enabled when you try to enable SAML and will instruct you to disable LDAP.

- 1. From the main menu, select Settings > User Management.
- 2. From the User Management page, click the **SAML** tab.



The SAML configuration page opens.




- 3. Complete the Identity Provider (IdP) section by either:
 - Uploading your IdP metadata file by dragging and dropping the file onto the field or using the browse button to locate the file saved on your local machine.



• Entering your IdP metadata file's URL in the **Provide IdP Metadata URL** field.


Connection Information - Identity Provider

Provide either an XML configuration file or a configuration URL below. When you provide one method, the other method will autopopulate.



Whichever method you choose to use will result in the auto-completion of the other field. **Example:** Uploading a metadata file will result in the IdP Metadata URL being populated with data parsed from the file.

4. Use either the Service Provider Connection URL or Service Provider Metadata file listed in the Connection Information - Service Provider Information section to provide your ThreatQ platform metadata to your Network Administrator to add ThreatQ as a service provider. The steps to add ThreatQ as a Service Provider may differ based on your environment - see the Adding ThreatQ as a Service Provider topic.





- 5. Check the **User Server Certificate and Key** option under the Platform Server Certificate Information section if your environment requires a certificate. You can upload the Certificate and .key file by either:
 - Drag and drop the file into the field.
 - Select browse to locate the file on your local machine.

You Network Administrator will need the certificate and key later when applying the ThreatQ platforms connection information supplied in step 4.

6. Complete the Mapping Permissions Levels section by providing a SAML Attribute Key and SAML Attribute Value for each ThreatQ user role. See the Setting Up LDAP Users/Groups for SAML topic for information on how to setup LDAP users and groups for SAML integration.

Mapping Permission Levels

(Note: You can not list the same SAML User Group for multiple permission levels)

Administrative Access	
SAML Attribute Key	SAML Attribute Value
Primary Contributor Access	
SAML Attribute Key	SAML Attribute Value
Read Only Access	
SAML Attribute Key	SAML Attribute Value

Mapping Notes:

- SAML cannot be used for Maintenance Accounts.
 - Local Maintenance Accounts cannot be mapped when enabling SAML.
 - If converting from LDAP authentication, LDAP groups that were mapped to the ThreatQ Maintenance role will have to be mapped to another user role.




- You cannot use the same SAML Key and Values for multiple roles.
- You do not have to map all ThreatQ roles but at least one role has to be mapped to use SAML. Example: Administrator and Primary Contributor will be mapped but the Read Only Access role will be blank.
- 7. Click on **Save** located at the bottom of the page.
- 8. Confirm that your network administrator has completed Adding ThreatQ as a Service Provider before proceeding with the final steps listed below.
- 9. Click on **Test Authentication** to confirm that the ThreatQ platform and your IdP can connect.
- 10. Click on the **Enable** toggle switch located at the top-right of the page to enable SAML.




Setting Up LDAP Users/Groups for SAML

The following steps detail how to set up LDAP users and groups for SAML integration.

- 1. Log into the Windows Server.
- 2. Start the Active Directory Users and Computers application from the Start Menu.




3. Navigate to and select the **Groups** folder under your LDAP domain.







4. Click on **Actions > New > Group**.



5. Enter in the **Group name** and click on **OK**.




6. Select the Users folder and click on Actions > New > User.







7. Enter in the **User Information** and click on **Next**.



8. Enter the Password and click on Next.




9. Confirm that the details are correct an then click on Finish.



10. Find and double-click on the newly created user to edit the **User Properties**.



11. Confirm that the E-Mail has the user's correct email address.







 $oldsymbol{\Lambda}$ It is important that the E-mail field be filled in order for the SSO integration to work with this user.



12. Navigate to the Member of tab and click on Add.




13. Enter the name of the group you created earlier in steps 4-5 in the field provided.



14. Click on Check Names to verify the group name and then click OK.



15. Verify that the User is now a member of the group.



16. Click **OK** to close the properties window.



Adding ThreatQ as a Service Provider

ThreatQ supports SAML configurations for all identity providers that are compliant with the Security Assertion Markup Language v2.

The sections listed in this topic serve as identity provider examples and include the required steps to add ThreatQ as a service provider for your IdP. Contact ThreatQ Support if your identity provider is not listed and you require assistance with configuration.

ADFS 2016

The steps below detail how to add ThreatQ as a service provider in ADFS 2016.

From your server manager:

- 1. Select AD FS under the Dashboard heading.
- 2. Click on the Tools option and select AD FS Management.
- 3. Navigate to the Relying Party Trusts folder In the left-hand directory.
- 4. Click on the Relying Party Trusts > Add Relying Party Trust under the Actions heading.
- 5. Leave the Claims Aware option selected and click on Start.




The Select Data Source section loads. Add Claims Provider Trust Wizard × Select Data Source Steps Select an option that this wizard will use to obtain data about this claims provider Welcome Import data about the claims provider published online or on a local network Select Data Source Use this option to import the necessary data and certificates from a claims provider organization that publishes its federation metadata online or on a local network Ready to Add Trust Finish Federation metadata address (host name or URL): Example: fs.fabrikam.com or https://fs.fabrikam.com/ Import data about the claims provider from a file Use this option to import the necessary data and certificates from a claims provider organization that has provided its federation metadata in a file. Federation metadata file location: Enter claims provider trust data manually Use this option to manually input the necessary data about this claims provider organization. < Previous Next > Cancel

- 6. Confirm that the first radio option, **Import data about the claims provider published online...**, is selected.
- 7. Paste the **Platform Connection URL** located on the ThreatQ SAML page, step 4 on the Configuring SAML topic, into the Federation Metadata Address field in the following format:

https://<your IdP hostname>/FederationMetadata/2007-06/FederationMetadata.xml

8. Click Next.

A popup warning will appear stating that some metadata cotent was skipped.



9. Click **Ok** to proceed.



- 10. Continue through the next few sections by clicking **Next** until you reach the Ready to Add Trust page.
- 11. Review the information listed in the multiple tabs provided. Confirm that the proper certificates are listed under the **Certificate** and **Signature** tabs and upload any that are missing.
- 12. Click Next.

The ThreatQ Relaying Party Trust has now been added. The next step to create 4 new Claims Rules for the new service provider.

Contact your Network Administrator to receive the appropriate group mapping.

- 13. Click on Add Rule.
- 14. Select the Send LDAP Attribute as Claims claim rule template and click Next.
- 15. Enter a name for the rule. **Example:** email and UID.
- 16. Select the **Active Directory** as the Attribute Store.

Active Directory must already be installed and enabled in order to complete this step

17. Add the following rows in the LDAP Mapping Attributes table:

LDAP ATTRIBUTE	OUTGOING CLAIM TYPE	NOTES
E-Mail-Addresses	email	
Email-Addresses	uid	Email-Addresses is the recommended value. However, you can use SAM-Account-Name as an alternative.

- 18. Click on **OK** to create the rule.
- 19. Click on Add Rule.
- 20. Select the **Send LDAP Attribute as Claims** claim rule template and click **Next**.
- 21. Enter a name for the rule. Example: Email.
- 22. Select the **Active Directory** as the Attribute Store.
- 23. Add the following row in the LDAP Mapping Attributes table:



LDAP ATTRIBUTE	OUTGOING CLAIM TYPE
E-Mail-Addresses	E-Mail Address

- 24. Click on **OK** to create the rule.
- 25. Click on Add Rule.
- 26. Select the Send LDAP Attribute as Claims claim rule template and click Next.
- 27. Enter a name for the rule. **Example:** Groups.
- 28. Select the **Active Directory** as the Attribute Store.
- 29. Add the following row in the LDAP Mapping Attributes table:

LDAP ATTRIBUTE	OUTGOING CLAIM TYPE
Token-Groups - Unqualified Names	SSO

- 30. Click on **OK** to create the rule.
- 31. Click on Add Rule.
- 32. Select the Transform an Incoming Claim claim rule template and click Next.
- 33. Enter a name for the rule. **Example:** Named ID Transform.
- 34. Complete the following fields:

FIELD	SELECTION
Incoming Claim Type	E-Mail Address
Outgoing Claim Type	Name ID
Outgoing Name ID Format	Email

- 35. Select the **Pass through all claim value** radio option.
- 36. Click on **OK** to create the rule.
- 37. Click **OK** to close the Issuance Transform Rules dialog box.



Azure AD

The steps below detail how to add ThreatQ as a service provider in Azure AD. This process is required in order to complete the SAML setup.

Setting Up the SAML App

- 1. Log in to the Azure portal with administrator permissions.
- 2. Go to Azure Active Directory > Enterprise applications
- 3. Click on +New Application then Non-gallery application.
- 4. Enter an application name such as **ThreatQ** then click **Add**.
- 5. Enter the Single Sign On URL and SP Entity ID as follows:



FIELD	VALUE	DESCRIPTION
ACS / Single Sign on URL	https:// threatq.example.com/api/ samle/acs	Assertion Consumer Service (ACS) is the ThreatQ URL + appended the "/api/saml/acs" string.
SP Entity ID	https:// threatq.example.com/api/ samle/metadata	This is the ThreatQ entity ID which is the ThreatQ URL + appended with the "/api/saml/metadata" string.

6. Set the Unique User identifier (Name ID) format to Email Address.


7. In the Additional claims section add uid and set the value as user.mail.




Both the username and uid attributes are required and must be mapped to the user's Email address.



8. You also need to add an attribute you want to map to the roles in ThreatQ. In this example we added a Claim and created a **Groups** attribute and mapped it to all **user.groups** assigned to the application. The group id the user belongs to is then included in the SAML assertion upon login.




When adding a group claim it is recommended to customize name as this is what is required to be entered on the ThreatQ side as the SAML Attribute Key. This should not contain a namespace otherwise the full claim name will need to be entered - see http://schemas.xmlsoap.org/ws/2005/05/identity/claims/givenname for more information. See the example below:



9. On the Assignments tab, verify that each of the users or groups that should have access have been assigned to the application.



10. Under **SAML Signing Certificate**, click the **Download** link for the **Certificate (Base64)** and the **Metadata** file. These files are required in steps 4 and 5 in the **Configuring SAML** topic.




Google G Suite

The steps below detail how to add ThreatQ as a service provider in Google's G Suite. This process is required in order to complete the SAML setup.

Setting Up the SAML App

- 1. Log into your Google Administrative Console.
- 2. Navigate to Apps > SAML Apps.
- 3. Click on the + icon located at the bottom-right on the page.
- 4. Select the **Setup my own custom app** option.






The Google IdP information page loads.



- 5. Click on Next.
- 6. Complete the *Basic Information for Your Custom App* fields:



7. Click on Next.




8. Complete the *Service Provider Details* fields:

FIELD	DESCRIPTION	EXAMPLE	
ACS URL	Assertion Consumer Service is your ThreatQ URL + appended the "/api/saml/acs" string.	https:// threatq.example.com/api/ saml/acs	
Entity ID	The Entity ID is your ThreatQ URL + appended with the "/api/saml/metadata" string.	https:// threatq.example.com/api/ saml/metadata	
Name ID Format	Set this field to Email . N/A		
	Service Provider Details Please provide service provider details to configure SSO for your Custom App. The ACS url and Entity ID are mandatory.		
ACS URL *			
Entity ID *			
Start URL Signed Response			
Name ID	Basic Information Primary Email		
Name ID Format	UNSPECIFIED		
PREVIOUS	CANCEL NEXT		

9. Click on **Next**.



The Attribute Mapping page loads.



10. Click on Add New Mapping.



The email and uid attributes must be mapped to the Primary Email field.

11. Create the **email** mapping:

ATTRIBUTE	TYPE	GOOGLE DATA FIELD
email	Basic Information	Primary Email

- 12. Click on Add New Mapping.
- 13. Create the **uid** mapping:

ATTRIBUTE	TYPE	GOOGLE DATA FIELD
uid	Basic Information	Primary Email

- 14. Click on Add New Mapping:
- 15. Create the **SSOGroup** mapping for ThreatQ roles:


ATTRIBUTE	TYPE	GOOGLE DATA FIELD
SSOGroup	Employee Details	< specific to your company >






Any attribute can be used for this mapping other than **Employee ID**. See the Creating custom attributes using the user schema Google support article for instructions on creating custom attributes to use for role mapping.

16. Your setup should now resemble the following screenshot:



- 17. Click on Finish.
- 18. Locate your new app under **Apps > SAML Apps**, click on the vertical ellipsis, and select **On for Everyone**.
- 19. Click on the app to open its settings details.
- 20. Click on Service Provider Details.

The Service Provider Details page opens.



- 21. Click on Manage Certificates.
- 22. Download the **certificate** and the **IdP Metadata** files that are required in steps 4 and 5 in the *Configuring SAML* section in the SAML Authentication topic.

Okta

The steps below detail how to add ThreatQ as a service provider in Okta. This process is required in order to complete the SAML setup.

- 1. Log into the Okta web application.
- 2. Click on the **Admin** button located to the top-right of the screen.



The Dashboard page loads.

3. Click on the **Applications** tab.

The Application page loads.

4. Click on Add Application.

The Add Applications page loads.

5. Click on Create New App.

The Create New Application dialog box opens.


- 6. Select **Web** from the Platform dropdown.
- 7. Select **SAML 2.0** for the Sign on method.
- 8. Click on the Create button.

The Create SAML Integration page opens with the General Settings tab selected.

- 9. Enter a name for the app in the **App Name** field.
- 10. Click on Next.

The Configure SAML section loads.

11. Complete the following fields:






FIELD	ENTRY/SELECTION	NOTES
Single sign on URL	https://< Host-name >.com/api/saml/acs	The Assertion Consumer Service (ACS) is your ThreatQ URL + appended the "/api/saml/acs" string.
Audience URI (SP Entity ID)	https://< Host-name >/ api/saml/metadata	The Audience URI is your ThreatQ URL + appended with the "/api/saml/metadata" string.
Name ID format	EmailAddress	
Application username	Email	ThreatQ requires that this field be set to Email.

12. Scroll down to the Attribute Statements section and add the following attribute:





13. Add the required attributes to the **Group Attribute Statements** that will be used to map Okta groups to ThreatQ user roles. In the example image below, an attribute called **SSORole** was created and is mapped to all Okta group names that starts with **TQ**.







See Okta's Custom Expression help article for additional information on assigning an attribute.

- 14. Click on **Preview the SAML Assertion** to confirm that the settings are correct.
- 15. Click on Next.

The Feedback section loads.

16. Select I'm a software vendor. I'd like to integrate my app with Okta and then click on Finish.

The Application details page loads.

- 17. Click on the **Assignments** tab.
- 18. Click on the **Assign** dropdown and select **Assign to Groups**.
- 19. Assign the app to groups that will be used to map ThreatQ roles.
- 20. Click on Save and Go Back.
- 21. Click on Done.
- 22. Click on the Sign On tab.
- 23. In the **Sign On Methods** section, right-click and download the **Identity Provider metadata** file.
- 24. Click on the View Setup Instructions button.



You will be able to review URL information such as the **Identity Provider Single Sign-On URL**, **Identity Provider Issuer**, and the **X.509 Certificate**.

25. Click on **Download Certificate**. The certificate and Identity Provider metadata file downloaded in step 23 are required in steps 4 and 5 in the Configuring SAML section of the SAML Authentication topic.



Index

Adversaries 307, 309, 308, 536, 537, 538, 539	Filter Sets 449, 453, 457, 460, 464, 462, 466, 468, 458, 473, 478, 474, 475, 477, 481, 482, 483, 484, 485
Air Gapped Data Sync (AGDS) 20, 20, 23, 30, 44	Indicator Defanging 377
Audit Log 543	Indicator Parsing Presets 302
Authentication 14, 15	Indicator Scoring 360
Automatic Expiration 122	Indicator Status 266, 364, 363
Bulk Actions 500, 502, 514, 506, 511, 508, 517	Indicator URL Normalization 365
Command Line Interface 49	Indicators 92, 346, 348, 347, 350
Commands 51	Integrations 223, 227, 232, 236, 240, 238, 242
Dashboard (default) 67, 66, 69, 68	Job Management 249
Dashboards (custom) 72, 96, 113, 119, 119	Licensing 253, 252
Data Collections 488	Logging In 17, 17
Data Controls 121	Navigation 254
Date and Time Format 301, 550	Notifications 257
Events 324, 326, 325	Object Details 526, 528, 529, 532, 534, 536, 541
Expiration 122, 125, 126, 123, 358, 357, 357, 508	Object Management 265
Exports 143, 144, 147, 144, 145, 142, 149, 166, 171	Proxy 293
Feed Health Notifications 258	Reports 284, 283, 283, 283, 284
Files 330, 334, 332	SAML 575, 587



Threat Library 441

Scoring 360	ThreatQ Backup/Restore 46
Scoring Algorithms 130	ThreatQ Critical System Processes 548
Search Filters 453, 473, 481, 482, 487	ThreatQ Platform 12
Search Results 496, 489, 488	Traffic Light Protocol (TLP) 134, 132, 132, 133
Searches 449	Troubleshooting Packages 545
Signatures 392	User Accounts 553, 554, 555, 557, 555, 557
SSL Certificates 546	User Lockout Settings 295
STIX 396, 396, 399, 413	User Roles 559, 559, 559, 560
Tasks 439, 439	Whitelisting 136