

# ThreatQuotient




## VMware Carbon Black Cloud Enterprise EDR Connector Guide

Version 1.2.0 rev-b

March 03, 2022

**ThreatQuotient**

11400 Commerce Park Dr., Suite 200  
Reston, VA 20191

 ThreatQ Supported

**Support**

Email: [support@threatq.com](mailto:support@threatq.com)

Web: [support.threatq.com](https://support.threatq.com)

Phone: 703.574.9893

# Contents

Support .....	4
Versioning.....	5
Introduction .....	6
Prerequisites .....	7
Carbon Black Cloud Enterprise EDR RBAC Permissions.....	7
Timezones .....	7
Installation.....	8
Configuration .....	11
Usage.....	13
Command Line Arguments.....	14
CRON.....	15
Change Log.....	16

# Warning and Disclaimer

ThreatQuotient, Inc. provides this document “as is”, without representation or warranty of any kind, express or implied, including without limitation any warranty concerning the accuracy, adequacy, or completeness of such information contained herein. ThreatQuotient, Inc. does not assume responsibility for the use or inability to use the software product as a result of providing this information.

Copyright © 2022 ThreatQuotient, Inc.

All rights reserved. This document and the software product it describes are licensed for use under a software license agreement. Reproduction or printing of this document is permitted in accordance with the license agreement.

# Support

This integration is designated as **ThreatQ Supported**.

**Support Email:** [support@threatq.com](mailto:support@threatq.com)

**Support Web:** <https://support.threatq.com>

**Support Phone:** 703.574.9893

Integrations/apps/add-ons designated as **ThreatQ Supported** are fully supported by ThreatQuotient's Customer Support team.

ThreatQuotient strives to ensure all ThreatQ Supported integrations will work with the current version of ThreatQuotient software at the time of initial publishing. This applies for both Hosted instance and Non-Hosted instance customers.



ThreatQuotient does not provide support or maintenance for integrations, apps, or add-ons published by any party other than ThreatQuotient, including third-party developers.

# Versioning

- Current integration version: 1.2.0
- Supported on ThreatQ versions  $\geq$  4.34.0

There are two versions of this integration:

- Python 2 version
- Python 3 version

# Introduction

The VMware Carbon Black Cloud Enterprise EDR for ThreatQ integration allows a user to export prioritized threat intelligence from ThreatQ into reports within VMware Carbon Black Cloud Enterprise EDR. VMware Carbon Black Cloud Enterprise EDR will match endpoint activity to the threat intelligence from ThreatQ and generate alerts.

VMware Carbon Black Cloud Enterprise EDR supports the following indicator types:

- IPAddress
- MD5
- SHA-256
- FQDN



The connector name and driver have changed as of version 1.2.0. In order to maintain backwards compatibility, you can use the old connector name in commands for running the connector along with the new name. All the commands used in this doc, excluding the installation steps, reference the new name `tq-conn-cb-enterprise-edr` but can be used interchangeably with the old name `tq-conn-cb-threat-hunter`.

You must use the `tq-conn-cb-threat-hunter` name when performing pip install commands.

# Prerequisites

Review the following prerequisites before installing the connector.

## Carbon Black Cloud Enterprise EDR RBAC Permissions

The following permissions, on the Carbon Black Cloud Enterprise EDR side, are required in order to successfully run the integration.

PERMISSION (.NOTATION NAME)	OPERATION
org.feeds	READ

## Timezones

You should ensure all ThreatQ devices are set to the correct time, time zone, and date (UTC is recommended), and using a clock source available to all.

To identify which time zone is closest to your present location, use the `timedatectl` command with the `list-timezones` command line option.

For example, enter the following command to list all available time zones in Europe:

```
timedatectl list-timezones | grep Europe
Europe/Amsterdam
Europe/Athens
Europe/Belgrade
Europe/Berlin
```

### Change Time Zone Example

Enter the following command, as root, to change the time zone to UTC:

```
timedatectl set-timezone UTC
```

# Installation

The connector can be installed from the ThreatQuotient repository with YUM credentials or offline via a .whl file.

**⚠ Upgrading Users** - Review the [Change Log](#) for updates to configuration parameters before updating. If there are changes to the configuration file (new/removed parameters), you must first delete the previous version's configuration file before proceeding with the install steps listed below. Failure to delete the previous configuration file will result in the connector failing.

**⚠** The connector name and driver have changed as of version 1.2.0. In order to maintain backwards compatibility, you can use the old connector name in commands for running the connector along with the new name. All the commands used in this doc reference the new name `tq-conn-cb-enterprise-edr` but can be used interchangeably with the old name `tq-conn-cb-threat-hunter`, with the only exception being the install commands.

You must use the `tq-conn-cb-threat-hunter` name when performing a pip install/upgrade.

1. Install the connector using one of the following methods:

## ThreatQ Repository

- a. Run the following command:

```
<> pip install tq_conn_cb_threat_hunter
```

## Offline via .whl file

To install this connector from a wheel file, the wheel file (.whl) will need to be copied via SCP into your ThreatQ instance.

- a. Download the connector whl file with its dependencies:

```
<> mkdir /tmp/tq_conn_cb_threat_hunter  
  
    pip download tq_conn_cb_threat_hunter -d  
  
    /tmp/tq_conn_cb_threat_hunter/
```



- b. Archive the folder with the .whl files:

```
<> tar -czvf tq_conn_cb_threat_hunter.tgz /tmp/  
tq_conn_cb_threat_hunter/
```

- c. Transfer all the whl files, the connector and all the dependencies, to the ThreatQ instance.
- d. Open the archive on ThreatQ:

```
<> tar -xvf tq_conn_cb_threat_hunter.tgz
```

- e. Install the connector on the ThreatQ instance.



The example assumes that all the whl files are copied to /tmp/conn on the ThreatQ instance.

```
<> pip install /tmp/conn/ tq_conn_cb_threat_hunter-<version>-  
<python version>-none-any.whl --no-index --find-links /  
tmp/conn/
```



Two drivers called tq-conn-cb-enterprise-edr and tq-conn-cb-threat-hunter will be installed. After installing with pip or setup.py, a script stub will appear in /usr/bin/tq-conn-cb-threat-hunter.

2. Once the application has been installed, a directory structure must be created for all configuration, logs and files, using the `mkdir -p` command. Use the commands below to create the required directories:

```
<> mkdir -p /etc/tq_labs/  
mkdir -p /var/log/tq_labs
```

3. Perform an initial run using the following command:

```
<> tq-conn-cb-enterprise-edr -v3 -ll /var/log/tq_labs/ -c /etc/  
tq_labs/
```



Due to the update to the integration name with version 1.2.0, users upgrading from 1.1.0 and earlier should use the following command to prevent a second instance from appearing in the ThreatQ UI.

```
<> tq -conn-cb-threat-hunter -v3 -ll /var/log/tq_labs/ -c /etc/  
tq_labs/ -n 'Carbon Black Threat Hunter'
```

4. Enter the following parameters when prompted:

PARAMETER	DESCRIPTION
ThreatQ Host	This is the host of the ThreatQ instance, either the IP Address or Hostname as resolvable by ThreatQ.
Client ID	This is the OAuth id that can be found at Settings Gear → User Management → API details within the user's details.
Email Address	This is the User in the ThreatQ System for integrations.
Password	The password for the above ThreatQ account.
Status	This is the default status for objects that are created by this Integration.

### Example Output

```
tq-conn-cb-enterprise-edr -v3 -ll /var/log/tq_labs/ -c /etc/tq_labs/  
ThreatQ Host: <ThreatQ Host IP or Hostname>  
Client ID: <ClientID>  
E-Mail Address: <EMAIL ADDRESS>  
Password: <PASSWORD>  
Status: Review  
Connector configured. Set information in UI
```

You will still need to [configure and then enable the connector](#).


# Configuration



ThreatQuotient does not issue API keys for third-party vendors. Contact the specific vendor to obtain API keys and other integration-related credentials.

To configure the integration:

1. Navigate to your integrations management page in ThreatQ.
2. Select the **Labs** option from the *Category* dropdown (optional).
3. Click on the integration to open its details page.
4. Enter the following parameters under the **Configuration** tab:

PARAMETER	DESCRIPTION
Enterprise EDR API FQDN	The FQDN to access Enterprise EDR's API.  The default is <code>defense.conferdeploy.net</code>
Enterprise EDR API Secret Key	Your Enterprise EDR API Secret Key for authentication.
Enterprise EDR API ID	Your Enterprise EDR API ID for authentication.
Enterprise EDR Organization Key	Your Enterprise EDR Organization Key for authentication.
Data Collection Names (Threat Library)	A comma-separated list of Threat Library collection names you want to export.
Report Tags	A comma-separated list of tags to add to the reports.   The tags will be added to each report.


---

PARAMETER	DESCRIPTION
ThreatQ Hostname or IP Address	This is the hostname or IP address of your ThreatQ instance in order to link back to it. This is typically the domain/IP that can be viewed in your browser's URL bar.

---

5. Review any additional settings available, make any changes if needed, and click on **Save**.
6. Click on the toggle switch, located above the *Additional Information* section, to enable it.

# Usage

 The connector name and driver have changed as of version 1.2.0. In order to maintain backwards compatibility, you can use the old connector name in commands for installing/running the connector along with the new name. All the commands used in this doc reference the new name `tq-conn-cb-enterprise-edr` but can be used interchangeably with the old name `tq-conn-cb-threat-hunter`.

Use the following command to execute the driver:

```
<> tq-conn-cb-enterprise-edr -v3 -ll /var/log/tq_labs/ -c /etc/tq_labs/
```

# Command Line Arguments

This connector supports the following custom command line arguments:

ARGUMENT	DESCRIPTION
<code>-h, --help</code>	Shows this help message and exits.
<code>-ll LOGLOCATION, --loglocation LOGLOCATION</code>	Sets the logging location for the connector. The location should exist and be writable by the current. A special value of 'stdout' means to log to the console (this happens by default).
<code>-c CONFIG, --config CONFIG</code>	This is the location of the configuration file for the connector. This location must be readable and writable by the current user. If no config file path is given, the current directory will be used. This file is also where some information from each run of the connector may be put (last run time, private oauth, etc.)
<code>-v {1,2,3}, --verbosity {1,2,3}</code>	This is the logging verbosity level where <b>3</b> means everything. The default setting is <b>1</b> (Warning).
<code>-ep, --external-proxy</code>	This allows you to use the proxy that is specified in the ThreatQ UI. This specifies an internet facing proxy, NOT a proxy to the TQ instance.
<code>-n NAME, --name NAME</code>	This sets the name for this connector. In some cases, it is useful to have multiple connectors of the same type executing against a single TQ instance. For example, the Syslog Exporter can be run against multiple target and multiple exports, each with their own name and configuration.
<code>-d, --no-differential</code>	If exports are used in this connector, this will turn 'off' the differential flag for the execution. This allows debugging and testing to be done on export endpoints without having to rebuild the

ARGUMENT	DESCRIPTION
	exports after the test. THIS SHOULD NEVER BE USED IN PRODUCTION.

## CRON

Automatic CRON configuration has been removed from this script. To run this script on a recurring basis, use CRON or some other jobs scheduler. The argument in the CRON script must specify the config and log locations.

Add an entry to your Linux crontab to execute the connector at a recurring interval. Depending on how quickly you need updates, this can be run multiple times a day (no more than once an hour) or a few times a week.

In the example below, the command will execute the connector every two hours.

1. Log into your ThreatQ host via a CLI terminal session.
2. Enter the following command:

```
<> crontab -e
```

This will enable the editing of the crontab, using vi. Depending on how often you wish the cronjob to run, you will need to adjust the time to suit the environment.

3. Enter the commands below:

### Every 2 Hours Example

```
<> 0 */2 * * * tq-conn-cb-enterprise-edr -c /etc/tq_labs/ -ll /  
var/log/tq_labs/ -v3
```

4. Save and exit CRON.

# Change Log

- **Version 1.2.0 rev-b**
  - Guide Update - Version 1.2.0 provides several updates to the configuration parameters. If you are upgrading from a previous version, you must first delete the previous version's configuration file before proceeding with the install steps. Failure to delete the previous configuration file will result in the connector failing.
- **Version 1.2.0 rev-a**
  - Revised the installation section of the user guide. The installation section previously stated that you can use either connector name to install the integration. You must use the `tq-conn-cb-threat-hunter` name to install or upgrade the connector. All other commands can use either of the new commands: `tq-conn-cb-threat-hunter` OR `tq-conn-cb-enterprise-edr`.
- **Version 1.2.0**
  - Rebranded connector name from Carbon Black Threat Hunter to VMware Carbon Black Cloud Enterprise EDR. The connector name and driver have changed as of version 1.2.0. In order to maintain backwards compatibility, you can use the old connector name in commands for installing/running it along with the new one. All the commands used in this doc reference the new name `tq-conn-cb-enterprise-edr` but can be used interchangeably with the old name `tq-conn-cb-threat-hunter`.
  - Added submission support for SHA-256 indicator types.
  - Added a new [Prerequisites](#) chapter for permissions and timezone requirements.
- **Version 1.1.0**
  - Added Python 3 support.
- **Version 1.0.0**
  - Initial Release